

Package: primePCA (via r-universe)

September 11, 2024

Type Package

Title Projected Refinement for Imputation of Missing Entries in PCA

Version 1.2

Date 2021-8-5

Author Ziwei Zhu, Tengyao Wang, Richard J. Samworth

Maintainer Ziwei Zhu <ziweiz@umich.edu>

Description Implements the primePCA algorithm, developed and analysed in Zhu, Z., Wang, T. and Samworth, R. J. (2019) High-dimensional principal component analysis with heterogeneous missingness. <[arXiv:1906.12125](#)>.

Imports softImpute, Matrix, MASS, methods

RoxygenNote 7.1.1

License GPL-3

NeedsCompilation no

Repository CRAN

Date/Publication 2021-08-05 15:10:02 UTC

Contents

col_scale	2
inverse_prob_method	2
primePCA	3
sin_theta_distance	4

Index	5
--------------	----------

col_scale	<i>Center and/or normalize each column of a matrix</i>
-----------	--

Description

Center and/or normalize each column of a matrix

Usage

```
col_scale(X, center = T, normalize = F)
```

Arguments

X	a numeric matrix with NAs or "Incomplete" matrix object (see softImpute package)
center	center each column of X if center == TRUE. The default value is TRUE.
normalize	normalize each column of X such that its sample variance is 1 if normalize == TRUE. The default value is False.

Value

a centered and/or normalized matrix of the same dimension as X .

inverse_prob_method	<i>Inverse probability weighted method for estimating the top K eigenspaces</i>
---------------------	---

Description

Inverse probability weighted method for estimating the top K eigenspaces

Usage

```
inverse_prob_method(X, K, trace.it = F, center = T, normalize = F)
```

Arguments

X	a numeric matrix with NAs or "Incomplete" matrix object (see softImpute package)
K	the number of principal components of interest
trace.it	report the progress if trace.it == TRUE
center	center each column of X if center == TRUE. The default value is TRUE.
normalize	normalize each column of X such that its sample variance is 1 if normalize == TRUE. The default value is False.

Value

Columnwise centered matrix of the same dimension as X .

Examples

```
X <- matrix(1:30 + .1 * rnorm(30), 10, 3)
X[1, 1] <- NA
X[2, 3] <- NA
v_hat <- inverse_prob_method(X, 1)
```

primePCA

primePCA algorithm

Description

primePCA algorithm

Usage

```
primePCA(
  X,
  K,
  V_init = NULL,
  thresh_sigma = 10,
  max_iter = 1000,
  thresh_convergence = 1e-05,
  thresh_als = 1e-10,
  trace.it = F,
  prob = 1,
  save_file = "",
  center = T,
  normalize = F
)
```

Arguments

X	an n -by- d data matrix with NA values
K	the number of the principal components of interest
V_init	an initial estimate of the top K eigenspaces of the covariance matrix of X . By default, primePCA will be initialized by the inverse probability method.
$thresh_sigma$	used to select the "good" rows of X to update the principal eigenspaces σ_* in the paper).
max_iter	maximum number of iterations of refinement
$thresh_convergence$	The algorithm is halted if the Frobenius-norm sine-theta distance between the two consecutive iterates

thresh_als	This is fed into thresh in svd.als of softImpute. is less than thresh_convergence.
trace.it	report the progress if trace.it = TRUE
prob	probability of reserving the "good" rows. prob == 1 means to reserve all the "good" rows.
save_file	the location that saves the intermediate results, including V_cur, step_cur and loss_all, which are introduced in the section of returned values. The algorithm will not save any intermediate result if save_file == "".
center	center each column of X if center == TRUE. The default value is TRUE.
normalize	normalize each column of X such that its sample variance is 1 if normalize == TRUE. The default value is False.

Value

a list is returned, with components V_cur, step_cur and loss_all. V_cur is a d -by- K matrix of the top K eigenvectors. step_cur is the number of iterations. loss_all is an array of the trajectory of MSE.

Examples

```
X <- matrix(1:30 + .1 * rnorm(30), 10, 3)
X[1, 1] <- NA
X[2, 3] <- NA
v_tilde <- primePCA(X, 1)$V_cur
```

sin_theta_distance *Frobenius norm sin theta distance between two column spaces*

Description

Frobenius norm sin theta distance between two column spaces

Usage

```
sin_theta_distance(V1, V2)
```

Arguments

V1 a matrix with orthonormal columns
V2 a matrix of the same dimension as V1 with orthonormal columns

Value

the Frobenius norm sin theta distance between two V1 and V2

Index

`col_scale`, 2

`inverse_prob_method`, 2

`primePCA`, 3

`sin_theta_distance`, 4