Package: blockmodels (via r-universe)

October 28, 2026

Type Package

Title Latent and Stochastic Block Model Estimation by a 'V-EM' Algorithm

Version 1.1.5

Date 2021-12-01

Author Jean-Benoist Leger <jbleger@hds.utc.fr>, Pierre Barbillon <pierre.barbillon@agroparistech.fr>, Julien Chiquet <julien.chiquet@inrae.fr>

Maintainer Jean-Benoist Leger <jbleger@hds.utc.fr>

Description Latent and Stochastic Block Model estimation by a Variational EM algorithm. Various probability distribution are provided (Bernoulli, Poisson...), with or without covariates.

License LGPL-2.1

Depends R (>= 3.4.0)

LinkingTo Rcpp, RcppArmadillo

RoxygenNote 7.1.1

Imports Rcpp, parallel, methods, digest

NeedsCompilation yes

Repository https://cran.r-universe.dev

Date/Publication 2021-12-01 10:20:09 UTC

RemoteUrl https://github.com/cran/blockmodels

RemoteRef HEAD

RemoteSha 271b3a7f1b87e7f1bbff73d8a8c34c038d273803

Contents

BM_bernoulli 2
BM_bernoulli_covariates 4
BM_bernoulli_covariates_fast 7

BM_bernoulli_multiplex 10
BM_gaussian 14
BM_gaussian_covariates 16
BM_gaussian_multivariate 19
BM_gaussian_multivariate_independent 22
BM_gaussian_multivariate_independent_homoscedastic 25
BM_poisson 28
BM_poisson_covariates 31

Index **35**

`BM_bernoulli` *Perform estimation on blockmodels for bernoulli probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_bernoulli(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

`membership_type`	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
`adj`	The adjacency matrix
`verbosity`	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

autosave — If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

plotting — Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

exploration_factor — Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min — Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max — Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction — Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores — Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
P<-matrix(runif(Q*Q),Q,Q)
M<-1*(matrix(runif(n*n),n,n)<Z%*%P%*%t(Z)) ## adjacency matrix

## estimation
```

```
my_model <- BM_bernoulli("SBM",M )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
P<-matrix(runif(Q*Q),Q,Q)
P[lower.tri(P)]<-t(P)[lower.tri(P)]
M<-1*(matrix(runif(n*n),n,n)<Z%*%P%*%t(Z)) ## adjacency matrix
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_bernoulli("SBM_sym",M )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
P<-matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M<-1*(matrix(runif(n[1]*n[2]),n[1],n[2])<Z1%*%P%*%t(Z2)) ## adjacency matrix

## estimation
my_model <- BM_bernoulli("LBM",M )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

`BM_bernoulli_covariates`

Perform estimation on blockmodels for bernoulli probability distribution aith covariates

---

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership, and impact vector of covariates.

Usage

```
## S4 method for signature 'new'
BM_bernoulli_covariates(
    membership_type,
    adj,
    covariates,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
covariates	Covariates matrix, or list of covariates matrices. Covariates matrix must have the same size than the adjacency matrix.
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.
autosave	If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.
plotting	Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.
exploration_factor	Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By

default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min
: Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max
: Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction
: Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores
: Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z<-diag(Q)%x%matrix(1,npc,1)
Mg<-8*matrix(runif(Q*Q),Q,Q)-4
Y1 <- matrix(runif(n*n),n,n)-.5
Y2 <- matrix(runif(n*n),n,n)-.5
M_in_expectation<-sigmo(Z%*%Mg%*%t(Z) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n*n),n,n)<M_in_expectation)

## estimation
my_model <- BM_bernoulli_covariates("SBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)


##
## SBM symmetric
##

## generation of one SBM_sym network
```

```
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z<-diag(Q)%x%matrix(1,npc,1)
Mg<-8*matrix(runif(Q*Q),Q,Q)-4
Mg[lower.tri(Mg)]<-t(Mg)[lower.tri(Mg)]
Y1 <- matrix(runif(n*n),n,n)-.5
Y2 <- matrix(runif(n*n),n,n)-.5
Y1[lower.tri(Y1)]<-t(Y1)[lower.tri(Y1)]
Y2[lower.tri(Y2)]<-t(Y2)[lower.tri(Y2)]
M_in_expectation<-sigmo(Z%*%Mg%*%t(Z) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n*n),n,n)<M_in_expectation)
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_bernoulli_covariates("SBM_sym",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)



##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mg<-8*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])-4
Y1 <- matrix(runif(n[1]*n[2]),n[1],n[2])-.5
Y2 <- matrix(runif(n[1]*n[2]),n[1],n[2])-.5
M_in_expectation<-sigmo(Z1%*%Mg%*%t(Z2) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n[1]*n[2]),n[1],n[2])<M_in_expectation)

## estimation
my_model <- BM_bernoulli_covariates("LBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_bernoulli_covariates_fast

Perform estimation on blockmodels for bernoulli probability distribution aith covariates

---

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership, and impact vector of covariates.

Usage

```
## S4 method for signature 'new'
BM_bernoulli_covariates_fast(
    membership_type,
    adj,
    covariates,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
covariates	Covariates matrix, or list of covariates matrices. Covariates matrix must have the same size than the adjacency matrix.
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.
autosave	If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.
plotting	Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.
exploration_factor	Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By

default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction
Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z<-diag(Q)%x%matrix(1,npc,1)
Mg<-8*matrix(runif(Q*Q),Q,Q)-4
Y1 <- matrix(runif(n*n),n,n)-.5
Y2 <- matrix(runif(n*n),n,n)-.5
M_in_expectation<-sigmo(Z%*%Mg%*%t(Z) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n*n),n,n)<M_in_expectation)

## estimation
my_model <- BM_bernoulli_covariates_fast("SBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)


##
## SBM symmetric
##

## generation of one SBM_sym network
```

```
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z<-diag(Q)%x%matrix(1,npc,1)
Mg<-8*matrix(runif(Q*Q),Q,Q)-4
Mg[lower.tri(Mg)]<-t(Mg)[lower.tri(Mg)]
Y1 <- matrix(runif(n*n),n,n)-.5
Y2 <- matrix(runif(n*n),n,n)-.5
Y1[lower.tri(Y1)]<-t(Y1)[lower.tri(Y1)]
Y2[lower.tri(Y2)]<-t(Y2)[lower.tri(Y2)]
M_in_expectation<-sigmo(Z%*%Mg%*%t(Z) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n*n),n,n)<M_in_expectation)
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_bernoulli_covariates_fast("SBM_sym",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)



##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
sigmo <- function(x){1/(1+exp(-x))}
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mg<-8*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])-4
Y1 <- matrix(runif(n[1]*n[2]),n[1],n[2])-.5
Y2 <- matrix(runif(n[1]*n[2]),n[1],n[2])-.5
M_in_expectation<-sigmo(Z1%*%Mg%*%t(Z2) + 5*Y1-3*Y2)
M<-1*(matrix(runif(n[1]*n[2]),n[1],n[2])<M_in_expectation)

## estimation
my_model <- BM_bernoulli_covariates_fast("LBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_bernoulli_multiplex *Perform estimation on blockmodels for multiplex binary networks*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_bernoulli_multiplex(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

`membership_type`
: The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'

`adj`
: The list of adjacency matrices. All matrices must have the same size

`verbosity`
: The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

`autosave`
: If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

`plotting`
: Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

`exploration_factor`
: Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction
Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
P00<-matrix(runif(Q*Q),Q,Q)
P10<-matrix(runif(Q*Q),Q,Q)
P01<-matrix(runif(Q*Q),Q,Q)
P11<-matrix(runif(Q*Q),Q,Q)
SumP<-P00+P10+P01+P11
P00<-P00/SumP
P01<-P01/SumP
P10<-P10/SumP
P11<-P11/SumP
MU<-matrix(runif(n*n),n,n)
M1<-1*(MU>Z%*%(P00+P01)%*%t(Z))
M2<-1*((MU>Z%*%P00%*%t(Z)) & (MU<Z%*%(P00+P01+P11)%*%t(Z))) ## adjacency matrices


## estimation
my_model <- BM_bernoulli_multiplex("SBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
```

```
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
P00<-matrix(runif(Q*Q),Q,Q)
P10<-matrix(runif(Q*Q),Q,Q)
P01<-matrix(runif(Q*Q),Q,Q)
P11<-matrix(runif(Q*Q),Q,Q)
SumP<-P00+P10+P01+P11
P00<-P00/SumP
P01<-P01/SumP
P10<-P10/SumP
P11<-P11/SumP
P00[lower.tri(P00)]<-t(P00)[lower.tri(P00)]
P01[lower.tri(P01)]<-t(P01)[lower.tri(P01)]
P10[lower.tri(P10)]<-t(P10)[lower.tri(P10)]
P11[lower.tri(P11)]<-t(P11)[lower.tri(P11)]
MU<-matrix(runif(n*n),n,n)
MU[lower.tri(MU)]<-t(MU)[lower.tri(MU)]
M1<-1*(MU>Z%*%(P00+P01)%*%t(Z))
M2<-1*((MU>Z%*%P00%*%t(Z)) & (MU<Z%*%(P00+P01+P11)%*%t(Z))) ## adjacency matrices


## estimation
my_model <- BM_bernoulli_multiplex("SBM_sym",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)


##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
P00<-matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
P10<-matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
P01<-matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
P11<-matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
SumP<-P00+P10+P01+P11
P00<-P00/SumP
P01<-P01/SumP
P10<-P10/SumP
P11<-P11/SumP
MU<-matrix(runif(n[1]*n[2]),n[1],n[2])
M1<-1*(MU>Z1%*%(P00+P01)%*%t(Z2))
```

```
M2<-1*((MU>Z1%*%P00%*%t(Z2)) & (MU<Z1%*%(P00+P01+P11)%*%t(Z2))) ## adjacency matrices


## estimation
my_model <- BM_bernoulli_multiplex("LBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_gaussian *Perform estimation on blockmodels for gaussian probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_gaussian(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

autosave — If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

plotting — Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

exploration_factor — Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min — Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max — Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction — Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores — Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu<-20*matrix(runif(Q*Q),Q,Q)
M<-matrix(rnorm(n*n,sd=10),n,n)+Z%*%Mu%*%t(Z) ## adjacency matrix

## estimation
```

```
my_model <- BM_gaussian("SBM",M )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu<-20*matrix(runif(Q*Q),Q,Q)
Mu[lower.tri(Mu)]<-t(Mu)[lower.tri(Mu)]
M<-matrix(rnorm(n*n,sd=10),n,n)+Z%*%Mu%*%t(Z) ## adjacency matrix
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_gaussian("SBM_sym",M )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mu<-20*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M<-matrix(rnorm(n[1]*n[2],sd=10),n[1],n[2])+Z1%*%Mu%*%t(Z2) ## adjacency matrix

## estimation
my_model <- BM_gaussian("LBM",M )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_gaussian_covariates

Perform estimation on blockmodels for gaussian probability distribution with covariates

---

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership and impact vector of covariates

Usage

```
## S4 method for signature 'new'
BM_gaussian_covariates(
    membership_type,
    adj,
    covariates,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
covariates	Covariates matrix, or list of covariates matrices. Covariates matrix must have the same size than the adjacency matrix.
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.
autosave	If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.
plotting	Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.
exploration_factor	Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By

default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

`explore_min` Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

`explore_max` Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

`exploration_direction`
Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

`ncores` Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu<-20*matrix(runif(Q*Q),Q,Q)
Y1 <- matrix(runif(n*n),n,n)
Y2 <- matrix(runif(n*n),n,n)
M<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu%*%t(Z)+4.2*Y1-1.6*Y2 ## adjacency matrix

## estimation
my_model <- BM_gaussian_covariates("SBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
```

```
Z<-diag(Q)%x%matrix(1,npc,1)
Mu<-20*matrix(runif(Q*Q),Q,Q)
Mu[lower.tri(Mu)]<-t(Mu)[lower.tri(Mu)]
Y1 <- matrix(runif(n*n),n,n)
Y2 <- matrix(runif(n*n),n,n)
Y1[lower.tri(Y1)]<-t(Y1)[lower.tri(Y1)]
Y2[lower.tri(Y2)]<-t(Y2)[lower.tri(Y2)]
M<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu%*%t(Z)+4.2*Y1-1.6*Y2 ## adjacency matrix
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_gaussian_covariates("SBM_sym",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mu<-20*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
Y1 <- matrix(runif(n[1]*n[2]),n[1],n[2])
Y2 <- matrix(runif(n[1]*n[2]),n[1],n[2])
M<-matrix(rnorm(n[1]*n[2],sd=5),n[1],n[2])+Z1%*%Mu%*%t(Z2)+4.2*Y1-1.6*Y2 ## adjacency matrix

## estimation
my_model <- BM_gaussian_covariates("LBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

`BM_gaussian_multivariate` *Perform estimation on blockmodels for multivariate gaussian probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
```

```
BM_gaussian_multivariate(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

`membership_type`
: The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'

`adj`
: The list of adjacency matrices. All matrices must have the same size

`verbosity`
: The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

`autosave`
: If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

`plotting`
: Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting=='', no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

`exploration_factor`
: Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

`explore_min`
: Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

`explore_max`
: Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction
: Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores
: Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-4*matrix(runif(Q*Q),Q,Q)
Mu2<-4*matrix(runif(Q*Q),Q,Q)
Noise1<-matrix(rnorm(n*n,sd=1),n,n)
Noise2<-matrix(rnorm(n*n,sd=1),n,n)
M1<- Z%*%Mu1%*%t(Z) + Noise1
M2<- Z%*%Mu2%*%t(Z) + 10*Noise1 + Noise2

## estimation
my_model <- BM_gaussian_multivariate("SBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-4*matrix(runif(Q*Q),Q,Q)
Mu2<-4*matrix(runif(Q*Q),Q,Q)
Noise1<-matrix(rnorm(n*n,sd=1),n,n)
Noise2<-matrix(rnorm(n*n,sd=1),n,n)
M1<- Z%*%Mu1%*%t(Z) + Noise1
M2<- Z%*%Mu2%*%t(Z) + 10*Noise1 + Noise2
M1[lower.tri(M1)]<-t(M1)[lower.tri(M1)]
```

```
M2[lower.tri(M2)]<-t(M2)[lower.tri(M2)]

## estimation
my_model <- BM_gaussian_multivariate("SBM_sym",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mu1<-4*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
Mu2<-4*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
Noise1<-matrix(rnorm(n[1]*n[2],sd=1),n[1],n[2])
Noise2<-matrix(rnorm(n[1]*n[2],sd=1),n[1],n[2])
M1<-Z1%*%Mu1%*%t(Z2) + Noise1 ## adjacency
M2<-Z1%*%Mu2%*%t(Z2) + 10*Noise1 + Noise2 ## adjacency

## estimation
my_model <- BM_gaussian_multivariate("LBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

`BM_gaussian_multivariate_independent` *Perform estimation on blockmodels for multivariate independent homoscedastic gaussian probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_gaussian_multivariate_independent(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
```

```
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The list of adjacency matrices. All matrices must have the same size
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.
autosave	If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.
plotting	Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.
exploration_factor	Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.
explore_min	Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.
explore_max	Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.
exploration_direction	Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.
ncores	Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of

the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-8*matrix(runif(Q*Q),Q,Q)
Mu2<-8*matrix(runif(Q*Q),Q,Q)
M1<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu1%*%t(Z) ## adjacency
M2<-matrix(rnorm(n*n,sd=10),n,n)+Z%*%Mu2%*%t(Z) ## adjacency

## estimation
my_model <- BM_gaussian_multivariate_independent("SBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-8*matrix(runif(Q*Q),Q,Q)
Mu2<-8*matrix(runif(Q*Q),Q,Q)
Mu1[lower.tri(Mu1)]<-t(Mu1)[lower.tri(Mu1)]
Mu2[lower.tri(Mu2)]<-t(Mu2)[lower.tri(Mu2)]
M1<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu1%*%t(Z) ## adjacency
M2<-matrix(rnorm(n*n,sd=10),n,n)+Z%*%Mu2%*%t(Z) ## adjacency
M1[lower.tri(M1)]<-t(M1)[lower.tri(M1)]
M2[lower.tri(M2)]<-t(M2)[lower.tri(M2)]

## estimation
my_model <- BM_gaussian_multivariate_independent("SBM_sym",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##
```

```
## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mu1<-8*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
Mu2<-8*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M1<-matrix(rnorm(n[1]*n[2],sd=5),n[1],n[2])+Z1%*%Mu1%*%t(Z2) ## adjacency
M2<-matrix(rnorm(n[1]*n[2],sd=10),n[1],n[2])+Z1%*%Mu2%*%t(Z2) ## adjacency

## estimation
my_model <- BM_gaussian_multivariate_independent("LBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

`BM_gaussian_multivariate_independent_homoscedastic` *Perform estimation on blockmodels for multivariate independent homoscedastic gaussian probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_gaussian_multivariate_independent_homoscedastic(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

`membership_type` The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'

`adj` The list of adjacency matrices. All matrices must have the same size

`verbosity` The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

`autosave` If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

`plotting` Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

`exploration_factor`
Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

`explore_min` Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

`explore_max` Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

`exploration_direction`
Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

`ncores` Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##
```

```
## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-4*matrix(runif(Q*Q),Q,Q)
Mu2<-4*matrix(runif(Q*Q),Q,Q)
M1<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu1%*%t(Z) ## adjacency
M2<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu2%*%t(Z) ## adjacency

## estimation
my_model <- BM_gaussian_multivariate_independent_homoscedastic("SBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
Mu1<-4*matrix(runif(Q*Q),Q,Q)
Mu2<-4*matrix(runif(Q*Q),Q,Q)
Mu1[lower.tri(Mu1)]<-t(Mu1)[lower.tri(Mu1)]
Mu2[lower.tri(Mu2)]<-t(Mu2)[lower.tri(Mu2)]
M1<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu1%*%t(Z) ## adjacency
M2<-matrix(rnorm(n*n,sd=5),n,n)+Z%*%Mu2%*%t(Z) ## adjacency
M1[lower.tri(M1)]<-t(M1)[lower.tri(M1)]
M2[lower.tri(M2)]<-t(M2)[lower.tri(M2)]

## estimation
my_model <- BM_gaussian_multivariate_independent_homoscedastic("SBM_sym",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
Mu1<-4*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
Mu2<-4*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M1<-matrix(rnorm(n[1]*n[2],sd=5),n[1],n[2])+Z1%*%Mu1%*%t(Z2) ## adjacency
M2<-matrix(rnorm(n[1]*n[2],sd=5),n[1],n[2])+Z1%*%Mu2%*%t(Z2) ## adjacency
```

```
## estimation
my_model <- BM_gaussian_multivariate_independent_homoscedastic("LBM",list(M1,M2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_poisson *Perform estimation on blockmodels for poisson probability distribution*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership

Usage

```
## S4 method for signature 'new'
BM_poisson(
    membership_type,
    adj,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

autosave
: If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

plotting
: Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

exploration_factor
: Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min
: Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max
: Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction
: Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores
: Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

#
# SBM
#

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
L<-70*matrix(runif(Q*Q),Q,Q)
M_in_expectation<-Z%*%L%*%t(Z)
M<-matrix(
    rpois(
```

```
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n,n)

## estimation
my_model <- BM_poisson("SBM",M )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
L<-70*matrix(runif(Q*Q),Q,Q)
L[lower.tri(L)]<-t(L)[lower.tri(L)]
M_in_expectation<-Z%*%L%*%t(Z)
M<-matrix(
    rpois(
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n,n)
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_poisson("SBM_sym",M )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
L<-70*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M_in_expectation<-Z1%*%L%*%t(Z2)
M<-matrix(
    rpois(
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n[1],n[2])

## estimation
my_model <- BM_poisson("LBM",M )
```

```
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

BM_poisson_covariates *Perform estimation on blockmodels for poisson probability distribution aith covariates*

Description

With the provided network and blockmodel type, estimate number of groups, parameters and node membership, and impact vector of covariates

Usage

```
## S4 method for signature 'new'
BM_poisson_covariates(
    membership_type,
    adj,
    covariates,
    verbosity=6,
    autosave='',
    plotting=character(0),
    exploration_factor=1.5,
    exploration_direction=numeric(0),
    explore_min=4,
    explore_max=Inf,
    ncores=detectCores())
```

Arguments

membership_type	The type of node membership, i.e. 'SBM', 'SBM_sym' or 'LBM'
adj	The adjacency matrix
covariates	Covariates matrix, or list of covariates matrices. Covariates matrix must have the same size than the adjacency matrix.
verbosity	The verbosity level, 0 means quiet. Level 1 display the phase of reinitialization. Level 2 display the level 1 and the ascending and descending phase for the number of groups. Level 3 display the level 2 and the number current number of groups which is estimated. Level 4 display the level 3 and the steps inside the estimation. Level 5 display the level 4, the current status of parallel running jobs and the current sub-step. Level 6 display level 5 and informations about ICL criteria found. Default is level 6. This parameter can be changed by accessing to the field $verbosity of the object.

autosave — If *autosave* != '', after each estimation, the model object is writed into file *autosave*. The model object is readable by the function *readRDS*. Use-it for long computation to allow restarting the estimation on system crash. You can use it to alanyze the partial results when the estimation is running. This parameter can be changed by accessing to the field $autosave of the object.

plotting — Control plot of ICL values while the estimation is running. If plotting==character(0) (the default), plots are done on screen, if plotting==", no plot are done, if plotting is a filename, plots are done in this filename. This parameter can be changed by accessing the field $plotting of the object.

exploration_factor — Control the exploration of the number of groups. The exploration is stop when the number of groups reach exploration factor times the current maximum. By default 1.5. This parameter can be changed by accessing the field $exploration_factor of the object.

explore_min — Explore to the explore_min number of groups even if the exploration_factor rule is satisfied. By default 4. This parameter can be changed by accessing the field $explore_min of the object.

explore_max — Stop exploration after explore_max number of group in any case. By default Inf. This parameter can be changed by accessing the field $explore_max of the object.

exploration_direction — Only for LBM membership. Control the exploration direction for groups number. When provided, the exploring strategy is made to explore the provided group number. Must be a vector of two integer value representing the row group number and the column group number.

ncores — Number of parallel jobs to launch different EM intializations. By default detectCores(). This parameter can be changed by accessing the field $ncores of the object. This parameters is used only on Linux. Parallism is disabled on other plateform. (Not working on Windows, not tested on Mac OS, not tested on *BSD.)

Examples

```
## Not run:

##
## SBM
##

## generation of one SBM network
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
L<-70*matrix(runif(Q*Q),Q,Q)
M_in_expectation_without_covariates<-Z%*%L%*%t(Z)
Y1 <- matrix(runif(n*n),n,n)
Y2 <- matrix(runif(n*n),n,n)
```

```
M_in_expectation<-M_in_expectation_without_covariates*exp(4.2*Y1-1.2*Y2)
M<-matrix(
    rpois(
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n,n)

## estimation
my_model <- BM_poisson_covariates("SBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

##
## SBM symmetric
##

## generation of one SBM_sym network, we re-use one produced for SBM
npc <- 30 # nodes per class
Q <- 3 # classes
n <- npc * Q # nodes
Z<-diag(Q)%x%matrix(1,npc,1)
L<-70*matrix(runif(Q*Q),Q,Q)
L[lower.tri(L)]<-t(L)[lower.tri(L)]
M_in_expectation_without_covariates<-Z%*%L%*%t(Z)
Y1 <- matrix(runif(n*n),n,n)
Y2 <- matrix(runif(n*n),n,n)
Y1[lower.tri(Y1)]<-t(Y1)[lower.tri(Y1)]
Y2[lower.tri(Y2)]<-t(Y2)[lower.tri(Y2)]
M_in_expectation<-M_in_expectation_without_covariates*exp(4.2*Y1-1.2*Y2)
M<-matrix(
    rpois(
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n,n)
M[lower.tri(M)]<-t(M)[lower.tri(M)]

## estimation
my_model <- BM_poisson_covariates("SBM_sym",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

##
## LBM
##

## generation of one LBM network
npc <- c(50,40) # nodes per class
Q <- c(2,3) # classes
n <- npc * Q # nodes
Z1<-diag(Q[1])%x%matrix(1,npc[1],1)
Z2<-diag(Q[2])%x%matrix(1,npc[2],1)
L<-70*matrix(runif(Q[1]*Q[2]),Q[1],Q[2])
M_in_expectation_without_covariates<-Z1%*%L%*%t(Z2)
```

```
Y1 <- matrix(runif(n[1]*n[2]),n[1],n[2])
Y2 <- matrix(runif(n[1]*n[2]),n[1],n[2])
M_in_expectation<-M_in_expectation_without_covariates*exp(4.2*Y1-1.2*Y2)
M<-matrix(
    rpois(
        length(as.vector(M_in_expectation)),
        as.vector(M_in_expectation))
    ,n[1],n[2])

## estimation
my_model <- BM_poisson_covariates("LBM",M,list(Y1,Y2) )
my_model$estimate()
which.max(my_model$ICL)

## End(Not run)
```

Index

BM_bernoulli, 2
BM_bernoulli_covariates, 4
BM_bernoulli_covariates_fast, 7
BM_bernoulli_multiplex, 10
BM_gaussian, 14
BM_gaussian_covariates, 16
BM_gaussian_multivariate, 19
BM_gaussian_multivariate_independent, 22
BM_gaussian_multivariate_independent_homoscedastic, 25
BM_poisson, 28
BM_poisson_covariates, 31