Package: mrgsolve (via r-universe)

October 28, 2026

Type Package

Title Simulate from ODE-Based Models

Version 2.0.1

Maintainer Kyle T Baron <kyleb@metrumrg.com>

Description Fast simulation from ordinary differential equation (ODE) based models typically employed in quantitative pharmacology and systems biology.

License GPL (>= 2)

URL https://mrgsolve.org/docs/, https://github.com/metrumresearchgroup/mrgsolve

BugReports https://github.com/metrumresearchgroup/mrgsolve/issues

Depends R (>= 4.1.0), methods

Imports Rcpp (>= 1.0.7), dplyr (>= 1.0.8), magrittr (>= 2.0.1), tibble (>= 3.1.6), rlang (>= 1.0.1), tidyselect (>= 1.1.1), lifecycle, glue

Suggests rstudioapi, lattice, testthat, xml2 (>= 1.3.2), rmarkdown, yaml, knitr, data.table (>= 1.14.2), pmxTools

LinkingTo Rcpp (>= 1.0.7), RcppArmadillo (>= 0.10.7.3.0), BH (>= 1.75.0-0)

RdMacros lifecycle

Encoding UTF-8

Language en-US

LazyLoad yes

NeedsCompilation yes

RoxygenNote 7.3.3

Collate 'RcppExports.R' 'utils.R' 'package.R' 'generics.R' 'class_tgrid.R' 'class_numericlist.R' 'class_matlist.R' 'class_ev.R' 'class_derived.R' 'class_mrgmod.R' 'class_mrgsims.R' 'Aaaa.R' 'annot.R' 'chain.R' 'class_build.R'

'class_evd.R' 'events.R' 'class_rx.R' 'compile.R'
'custom-tol.R' 'data_set.R' 'datasets.R'
'dsl-preprocess-addin.R' 'env.R' 'funset.R'
'handle_spec_block.R' 'idata_set.R' 'init.R' 'inven.R'
'knobs.R' 'matlist.R' 'matrix.R' 'mcode.R' 'model_include.R'
'modlib.R' 'modspec.R' 'mread.R' 'mrgindata.R' 'mrgsim_q.R'
'mrgsims.R' 'mrgsolve.R' 'mwrite.R' 'nm-mode.R' 'nmxml.R'
'param.R' 'print.R' 'realize_addl.R' 'relabel.R' 'update.R'
'workflows.R'

Author Kyle T Baron [aut, cre] (ORCID:
<https://orcid.org/0000-0001-7252-5656>), Bill Gillespie [ctb],
Charles Margossian [ctb], Devin Pastoor [ctb], Bill Denney
[ctb] (ORCID: <https://orcid.org/0000-0002-5759-428X>), Dilawar
Singh [ctb], Felicien Le Louedec [ctb] (ORCID:
<https://orcid.org/0000-0003-3699-2729>), Timothy Waterhouse
[ctb] (ORCID: <https://orcid.org/0000-0002-0954-9660>), Kyle
Meyer [ctb], Metrum Research Group [cph]

Repository https://cran.r-universe.dev

Date/Publication 2026-05-20 08:39:01 UTC

RemoteUrl https://github.com/cran/mrgsolve

RemoteRef HEAD

RemoteSha 616a8becbdabcaa763279e574fa7426b576b7518

Contents

mrgsolve-package 4
$,ev-method 7
$,mrgmod-method 8
aboutsolver 8
as.ev 9
as.list,mrgmod-method 10
as.list,mrgsims-method 12
as_bmat 13
as_data_set 14
as_deslist 16
BLOCK_PARSE 17
blocks 19
c,matlist-method 20
c,tgrid-method 20
carry_out 21
check_data_names 22
cmtn 23
code 24
collapse_matrix 24
collapse_omega 25
custom_tol 26

data_set . . . 27
design . . . 29
details . . . 30
dsl_preprocess . . . 31
env_eval . . . 33
env_get . . . 33
env_ls . . . 34
env_update . . . 35
ev . . . 35
ev_assign . . . 37
ev_days . . . 38
ev_rep . . . 39
ev_repeat . . . 40
ev_rx . . . 41
ev_seq . . . 42
evd . . . 44
exdatasets . . . 45
expand.idata . . . 46
expand_observations . . . 47
get_tol . . . 48
idata_set . . . 48
init . . . 50
inventory . . . 51
is.mrgmod . . . 52
is.mrgsims . . . 53
knobs . . . 53
lctran . . . 54
loadso . . . 55
matrix_helpers . . . 56
mcode . . . 57
mcRNG . . . 58
modlib . . . 58
modlib_details . . . 59
modlib_pk . . . 61
modlib_pkpd . . . 61
modlib_tmdd . . . 62
modlib_viral . . . 63
mread . . . 64
mread_yaml . . . 67
mrgsim . . . 68
mrgsim_q . . . 73
mrgsim_variants . . . 74
mrgsims_dplyr . . . 76
mrgsims_modify . . . 77
mutate.ev . . . 78
mwrite_cpp . . . 79
mwrite_yaml . . . 80
names,mrgmod-method . . . 81

nmext . . . 81
nmxml . . . 83
numerics_only . . . 85
obsaug . . . 85
obsonly . . . 86
omega . . . 86
outvars . . . 88
param . . . 88
param_tags . . . 90
PKMODEL . . . 91
plot_mrgsims . . . 93
plot_sims . . . 95
qsim . . . 96
read_nmext . . . 98
realize_addl . . . 99
Req . . . 100
reserved . . . 101
reset_tol . . . 102
revar . . . 103
see . . . 103
sigma . . . 104
simargs . . . 105
soloc . . . 106
solversettings . . . 107
summary.mrgmod . . . 107
tscale . . . 108
update . . . 109
use_custom_tol . . . 111
valid_data_set . . . 112
valid_idata_set . . . 113
within . . . 114
zero_re . . . 115

Index **116**

`mrgsolve-package` *mrgsolve: Simulate from ODE-Based Models*

Description

mrgsolve is an R package maintained under the auspices of Metrum Research Group that facilitates simulation from models based on systems of ordinary differential equations (ODE) that are typically employed for understanding pharmacokinetics, pharmacodynamics, and systems biology and pharmacology. mrgsolve consists of computer code written in the R and C++ languages, providing an interface to a C++ translation of the lsoda differential equation solver. See aboutsolver for more information.

Resources

- Main mrgsolve resource page: https://mrgsolve.org
- User guide: https://mrgsolve.org/user_guide/
- Package documentation and vignettes: https://mrgsolve.org/docs/

Package-wide options

- `mrgolve.project`: sets the default project director (`mread()`)
- `mrgsolve.soloc`: sets the default package build directory (`mread()`)
- `mrgsolve_mread_quiet`: don't print messages during `mread()`
- `mrgsolve.update.strict`: this option has been deprecated; use the `strict` argument to `update()` instead

Author(s)

Maintainer: Kyle T Baron <kyleb@metrumrg.com> (ORCID)

Other contributors:

- Bill Gillespie [contributor]
- Charles Margossian [contributor]
- Devin Pastoor [contributor]
- Bill Denney (ORCID) [contributor]
- Dilawar Singh [contributor]
- Felicien Le Louedec (ORCID) [contributor]
- Timothy Waterhouse (ORCID) [contributor]
- Kyle Meyer [contributor]
- Metrum Research Group [copyright holder]

See Also

Useful links:

- https://mrgsolve.org/docs/
- https://github.com/metrumresearchgroup/mrgsolve
- Report bugs at https://github.com/metrumresearchgroup/mrgsolve/issues

Examples

```
## example("mrgsolve")

mod <- mrgsolve::house(delta=0.1)  %>% param(CL=0.5)

events <-  ev(amt=1000, cmt=1, addl=5, ii=24)

events
```

```
mod

see(mod)

## Not run:
stime(mod)

## End(Not run)
param(mod)

init(mod)

out <- mod %>% ev(events) %>% mrgsim(end=168)

head(out)
tail(out)
dim(out)

plot(out, GUT+CP~.)

sims <- as.data.frame(out)

t72 <- dplyr::filter(sims, time==72)

str(t72)

idata <- data.frame(ID=c(1,2,3), CL=c(0.5,1,2),VC=12)
out <- mod %>% ev(events) %>% mrgsim(end=168, idata=idata, req="")
plot(out)

out <- mod %>% ev(events) %>% mrgsim(carry_out="amt,evid,cmt,CL")
head(out)

ev1 <- ev(amt=500, cmt=2,rate=10)
ev2 <- ev(amt=100, cmt=1, time=54, ii=8, addl=10)
events <- c(ev1+ev2)
events

out <- mod %>% ev(events) %>% mrgsim(end=180, req="")
plot(out)


## "Condensed" data set
data(extran1)
extran1

out <- mod %>% data_set(extran1) %>% mrgsim(end=200)

plot(out,CP~time|factor(ID))


## idata
```

```
data(exidata)

out <-
  mod %>%
  ev(amt=1000, cmt=1) %>%
  idata_set(exidata) %>%
  mrgsim(end=72)

plot(out, CP~., as="log10")


# Internal model library
## Not run:
mod <- mread("irm1", modlib())

mod

x <- mod %>% ev(amt=300, ii=12, addl=3) %>% mrgsim


## End(Not run)
```

`$,ev-method` *Select columns from an ev object*

Description

Select columns from an ev object

Usage

```
## S4 method for signature 'ev'
x$name

## S4 method for signature 'ev'
x[[i, exact = TRUE]]
```

Arguments

`x`	ev object
`name`	column to select
`i`	an element to select
`exact`	not used

$,mrgmod-method *Select parameter values from a model object*

Description

The $ and [[operators get the value of a single parameter in the model. The [gets several values, returning a named list.

Usage

```
## S4 method for signature 'mrgmod'
x$name

## S4 method for signature 'mrgmod'
x[[i, exact = TRUE]]

## S4 method for signature 'mrgmod'
x[i]
```

Arguments

x	mrgmod object
name	parameter to take
i	an element to select
exact	not used

aboutsolver *About the lsoda differential equation solver used by mrgsolve*

Description

The differential equation solver is a C++ translation of DLSODA from ODEPACK. The C++ translation was created by Dilawar Singh and hosted here https://github.com/dilawar/libsoda-cxx/. As we understand the history of the code, Heng Li was also involved in early versions of the code written in C. There was a potentially-related project hosted here https://github.com/sdwfrost/liblsoda/.

Details

The C++ translation by Dilawar Singh contains functions that appear to be based on BLAS and LAPACK routines. These functions have been renamed to be distinct from the respective BLAS and LAPACK function names. References are given in the section below.

History

The following history was recorded in the source code published by Dilawar Singh:

```
/*
* HISTORY:
* This is a CPP version of the LSODA library for integration into MOOSE
somulator.
* The original was aquired from
* http://www.ccl.net/cca/software/SOURCES/C/kinetics2/index.shtml and modified
by
* Heng Li <lh3lh3@gmail.com>. Heng merged several C files into one and added a
* simpler interface. [Available
here](http://lh3lh3.users.sourceforge.net/download/lsoda.c)

* The original source code came with no license or copyright
* information. Heng Li released his modification under the MIT/X11 license. I
* maintain the same license. I have removed quite a lot of text/comments from
* this library. Please refer to the standard documentation.
*
* Contact: Dilawar Singh <dilawars@ncbs.res.in>
*/
```

References

1. LAPACK: https://netlib.org/lapack/
2. BLAS: https://netlib.org/blas/

`as.ev` *Coerce an object to class ev*

Description

Use this function to convert a data frame to an event object.

Usage

```
as.ev(x, ...)

## S4 method for signature 'data.frame'
as.ev(x, keep_id = TRUE, clean = FALSE, ...)

## S4 method for signature 'ev'
as.ev(x, ...)
```

Arguments

x	an object to coerce.
...	not used.
keep_id	if TRUE, ID column is retained if it exists.
clean	if TRUE, only dosing or ID information is retained in the result.

Details

If CMT (or cmt) is missing from the input, it will be set to 1 in the event object.

If TIME (or time) is missing from the input, it will be set to 0 in the event object.

If EVID (or evid) is missing from the input, it will be set to 1 in the event object.

Value

An object with class ev.

Examples

```
data <- data.frame(AMT = 100)

as.ev(data)

as.ev(data, clean = TRUE)
```

---

as.list,mrgmod-method *Coerce a model object to list*

Description

Coerce a model object to list

Usage

```
## S4 method for signature 'mrgmod'
as.list(x, deep = FALSE, ...)
```

Arguments

x	a model object.
deep	if TRUE, extra information is returned in the output list (see **Details**).
...	not used.

Details

If deep is TRUE, then the values for trans, advan, and mindt are returned as well as a summary of internal model functions (with a call to mrgsolve:::funset()).

Value

A named list containing formatted contents from `x`.

Slots

- `npar`: number of parameters
- `neq`: number of compartments or differential equations
- `pars`: names of model parameters
- `covariates`: names of parameters identified as covariates
- `cmt`: names of model compartments
- `param`: the parameter list
- `init`: initial condition list
- `omega`: `$OMEGA` matrices, as a `matlist` object
- `sigma`: `$SIGMA` matrices, as a `matlist` object
- `fixed`: named list of `$FIXED` values
- `model`: model name
- `project`: model project directory
- `soloc`: directory where the model is being built
- `sodll`: complete path to the model shared object
- `cfile`: path for the model source code file
- `shlib`: list of compilation information
- `start`: simulation start time
- `end`: simulation end time
- `delta`: simulation time step
- `add`: additional simulation times
- `capture`: names of captured data items
- `request`: compartments requested upon simulation
- `cmti`: named indices for current output compartments
- `capturei`: named indices for current output capture
- `random`: names and labels of `$OMEGA` and `$SIGMA`
- `code`: model source code from `cfile`
- `details`: model details data frame
- `nm_import`: a character vector listing the names of nonmem output files that were read to import estimates from a completed nonmem run
- `cpp_variables`: a data frame listing variables internal to the model cpp file
- `atol`: see solversettings
- `rtol`: see solversettings
- `ss_atol`: absolute tolerance to use when advancing to PK steady state

- ss_rtol: relative tolerance to use when advancing to PK steady state
- custom_atol: absolute tolerances, one for each compartment
- custom_rtol: relative tolerances, one for each compartment
- maxsteps: see solversettings
- hmin: see solversettings
- hmax: see solversettings
- itol: 1 (use scalar values) or 4 (use customized values)
- itol_type: either "scalar" (itol = 1) or "custom" (itol = 4)
- envir: the model environment
- plugins: plugins invoked in the model
- digits: number of digits to request in simulated data
- tscale: multiplicative scalar for time in results only
- mindt: simulation output time below which there model will assume to have not advanced
- preclean: logical indicating to clean up compilation artifacts prior to compiling
- debug: print debugging information during simulation run
- verbose: print extra information during setup for model run

Examples

```
mod <- mrgsolve::house()
l <- as.list(mod)
```

---

as.list,mrgsims-method

Coerce an mrgsims object to list

Description

Coerce an mrgsims object to list

Usage

```
## S4 method for signature 'mrgsims'
as.list(x, ...)
```

Arguments

x	an mrgsims object.
...	not used.

as_bmat *Coerce R objects to block or diagonal matrices*

Description

These are simple functions that may be helpful to create the matrix objects that mrgsolve expects. Functions are named based on whether they create a diagonal matrix (d), a block matrix (b), or a a correlation matrix (c).

Usage

```
as_bmat(x, ...)

## S4 method for signature 'list'
as_bmat(x, ...)

## S4 method for signature 'numeric'
as_bmat(x, pat = "*", ...)

## S4 method for signature 'data.frame'
as_bmat(x, pat = "*", cols = NULL, ...)

## S4 method for signature 'ANY'
as_bmat(x, ...)

as_dmat(x, ...)

## S4 method for signature 'list'
as_dmat(x, ...)

## S4 method for signature 'ANY'
as_dmat(x, ...)

## S4 method for signature 'numeric'
as_dmat(x, pat = "*", ...)

## S4 method for signature 'data.frame'
as_dmat(x, pat = "*", cols = NULL, ...)

as_cmat(x, ...)
```

Arguments

x	data frame or list.
...	arguments passed to dmat() or cmat().
pat	regular expression, character.
cols	column names to use instead of pat.

Details

Use `as_dmat()` to create a diagonal matrix, `as_bmat()` to create a block matrix, and `as_cmat()` to create a block matrix where off-diagonal elements are understood to be correlations rather than covariances. `as_cmat()` uses `as_bmat()` to form the matrix and then converts off-diagonal elements to covariances before returning.

The methods for `data.frame` will work down the rows of the data frame and make the appropriate matrix from the data in each row. The result is a list of matrices.

Value

A numeric matrix for list and numeric methods. For data.frames, a list of matrices are returned.

See Also

`bmat()`, `dmat()`, `cmat()`

Examples

```
df <- data.frame(
  OMEGA1.1 = c(1,2),
  OMEGA2.1 = c(11,22),
  OMEGA2.2 = c(3,4),
  SIGMA1.1 = 1,
  FOO=-1
)

as_bmat(df, "OMEGA")
as_dmat(df,"SIGMA")
as_dmat(df[1,],"OMEGA")
```

---

as_data_set *Create a simulation data set from ev objects or data frames*

Description

The goal is to take a series of event objects or data frames and combine them into a single data frame that can be passed to `data_set()`.

Usage

```
as_data_set(x, ...)

## S4 method for signature 'ev'
as_data_set(x, ...)

## S4 method for signature 'data.frame'
as_data_set(x, ...)
```

Arguments

x	an ev object or data frame.
...	additional ev objects or data frames.

Details

Each event object or data frame is added to the data frame as an ID or set of IDs that are distinct from the IDs in the other event objects. Note that including ID argument to the ev() call where length(ID) is greater than one will render that set of events for all of IDs that are requested.

When determining the case for output names, the case attribute for the first ev object passed will be used to set the case for the output data.frame. In the event x is a data frame, the case of special column names (like amt/AMT or cmt/CMT) in the first data frame will be assessed and the case in the output data frame will be determined based on the relative numbers of lower or upper names.

To get a data frame with one row (event) per ID, look at expand.ev().

Value

A data frame suitable for passing into data_set(). The columns will appear in a standardized order.

See Also

expand.ev(), expand.evd(), ev(), evd(), uctran(), lctran()

Examples

```
a <- ev(amt = c(100,200), cmt=1, ID = seq(3))
b <- ev(amt = 300, time = 24, ID = seq(2))
c <- ev(amt = 1000, ii = 8, addl = 10, ID = seq(3))

as_data_set(a, b, c)

d <- evd(amt = 500)

as_data_set(d, a)

# Output will have upper case nmtran names
as_data_set(
  data.frame(AMT = 100, ID = 1:2),
  data.frame(amt = 200, rate = 5, cmt = 2)
)

# Instead of this, use expand.ev
as_data_set(ev(amt = 100), ev(amt = 200), ev(amt = 300))
```

`as_deslist` *Create a list of designs from a data frame*

Description

Create a list of designs from a data frame

Usage

```
as_deslist(data, descol = "ID")
```

Arguments

`data`	input data set; see **Details**.
`descol`	character column name to be used for design groups.

Details

The input data set must have a column with the same name as the value of `descol`. Other column names should be `start` (the time of the first observation), `end` (the time of the last observation), `delta` (the time steps to take between `start` and `end`), and `add` (other, ad-hoc times). Note that `add` might be a `list-column` to get a vector of times for each time grid object.

Value

The function returns a list of `tgrid` objects, one for each unique value found in `descol`.

Examples

```
idata <- tibble::tibble(ID=1:4, end=seq(24,96,24), delta=6,
add=list(c(122,124,135),c(111), c(99),c(88)))

idata <- dplyr::mutate(idata, GRP = ID %%2)

idata

l <- as_deslist(idata,"GRP")

l

lapply(l,stime)

lapply(as_deslist(idata, "ID"),stime)
```

BLOCK_PARSE *Functions to parse code blocks*

Description

Most of the basic blocks are listed in this help topic. But see also PKMODEL() which has more-involved options and is documented separately.

Usage

```
PARAM(
  x,
  env,
  pos = 1,
  annotated = FALSE,
  object = NULL,
  as_object = FALSE,
  covariates = FALSE,
  input = FALSE,
  tag = NULL,
  ...
)

FIXED(x, env, pos = 1, annotated = FALSE, ...)

THETA(
  x,
  env,
  pos = 1,
  annotated = FALSE,
  object = NULL,
  as_object = FALSE,
  name = "THETA",
  fill = NULL,
  ...
)

INIT(x, env, pos = 1, annotated = FALSE, object = NULL, as_object = FALSE, ...)

CMT(
  x,
  env,
  pos = 1,
  annotated = FALSE,
  object = NULL,
  as_object = FALSE,
  number = NULL,
```

```
  prefix = "A",
  ...
)

CAPTURE(x, env, pos = 1, annotated = FALSE, etas = NULL, ...)

HANDLEMATRIX(
  x,
  env,
  pos = 1,
  annotated = FALSE,
  object = NULL,
  as_object = FALSE,
  name = "...",
  type = NULL,
  oclass = "",
  prefix = "",
  labels = NULL,
  unlinked = FALSE,
  ...
)
```

Arguments

x	data
env	parse environment
pos	block position
annotated	logical
object	the name of an object in ENV
as_object	indicates that object code is being provided
covariates	logical; mark as covariates and potentially required data input
input	logical; mark as potentially required data input
tag	space or comma-separated user-defined tags for the parameter block
...	passed
name	block name
fill	deprecated; not used
number	number of compartments to create
prefix	a prefix to add to the label
etas	allows for block capture of ETAs in the simulated output; this should be R code that will get parsed and evaluated; the result should be an integer-like vector which identifies which ETAs will be captured.
type	internal use
oclass	internal use
labels	aliases to use for simulated ETA values
unlinked	internal use

Details

When using `object` or `as_object` populate the block contents, the following types are required

- `PARAM`: a named list
- `INIT` : a named list
- `THETA` : a numeric vector; names are ignored
- `CMT`: a character vector
- `OMEGA`: matrix; set rownames on the matrix to create ETA labels; setting rownames is the only way to specify `labels` when working through the `object` or `as_object` directives
- `SIGMA`: matrix; set rownames on the matrix to create EPS labels; setting rownames is the only way to specify `labels` when working through the `object` or `as_object` directives

See Also

`PKMODEL()`

---

blocks *Return the code blocks from a model specification file*

Description

Return the code blocks from a model specification file

Usage

```
blocks(x, ...)

## S4 method for signature 'mrgmod'
blocks(x, ...)

## S4 method for signature 'character'
blocks(x, ...)
```

Arguments

`x`	model object or path to model specification file
`...`	passed along

Examples

```
mod <- mrgsolve::house()
mod %>% blocks
mod %>% blocks(PARAM,TABLE)
```

c,matlist-method *Operations with matlist objects*

Description

Operations with matlist objects

Usage

```
## S4 method for signature 'matlist'
c(x, ..., recursive = FALSE)
```

Arguments

x	a matlist object.
...	other matlist objects.
recursive	not used.

c,tgrid-method *Operations with tgrid objects*

Description

Operations with tgrid objects

Usage

```
## S4 method for signature 'tgrid'
c(x, ..., recursive = FALSE)

## S4 method for signature 'tgrids'
c(x, ..., recursive = FALSE)

## S4 method for signature 'tgrid,numeric'
e1 + e2

## S4 method for signature 'tgrid,numeric'
e1 * e2

## S4 method for signature 'tgrids,numeric'
e1 + e2

## S4 method for signature 'tgrids,numeric'
e1 * e2
```

Arguments

x	a tgrid object.
...	additional tgrid objects.
recursive	not used.
e1	tgrid or tgrids object
e2	numeric value

---

carry_out *Select items to carry into simulated output*

Description

When items named in this function are found in the input data set (either data_set() or idata_set()), they are copied into the simulated output. Special items like evid or amt or the like are not copied from the data set per se, but they are copied from datarecord objects that are created during the simulation.

Usage

```
carry_out(x, ...)

carry.out(x, ...)
```

Arguments

x	model object.
...	unquoted names of data items to copy into the simulated output.

Details

There is also a carry_out argument to mrgsim() that can be set to accomplish the same thing as a call to carry_out in the pipeline.

carry.out and carry_out both do the same thing; using the underscore version is now preferred.

Examples

```
mod <- mrgsolve::house()

e <- ev(amt = 100, ii = 6, addl = 3, WT = 70, dose = amt)

out <- mod %>% ev(e) %>% carry_out(amt, dose, WT) %>% mrgsim()

head(out)
```

check_data_names *Check input data set names against model parameters*

Description

Use this function to check names of input data sets against parameters that have been assigned different tags. Assignment is made in the model specification file. This is useful to alert the user to misspelled or otherwise misspecified parameter names in input data sets. See `param_tags()` for information on associating tags with parameters.

Usage

```
check_data_names(
  data,
  x,
  check_covariates = TRUE,
  check_inputs = TRUE,
  tags = NULL,
  mode = c("warn", "error", "inform"),
  silent = FALSE
)
```

Arguments

`data`	a data frame or other object with names to check.
`x`	a model object.
`check_covariates`	logical; if `TRUE`, check `data` for parameter names carrying the `covariates` tag.
`check_inputs`	logical; if `TRUE`, check `data` for parameter names carrying the `input` tag.
`tags`	a character vector of user-defined parameter tags to require in `data`; this may be a comma- or space-separated string (e.g. `"tag1,tag2"`).
`mode`	the default is to `"warn"` the user when `data` is missing some expected column names; alternatively, use `"error"` to issue an error or `"inform"` to generate a message when `data` is missing some expected column names.
`silent`	silences message on successful check.

Details

By default, `data` will be checked for parameters with the `covariates` or `input` tags; these checks can be bypassed with the `check_covariates` and `check_inputs` arguments. When a parameter name is missing from `data` the user will be warned by default. Use `mode = "error"` to generate an error instead of a warning and use `mode = "inform"` to simply be informed. When the user has not tagged any parameters for checking, there will either be a warning (default) or an error (when `mode = "error"`).

It is an error to request a parameter tag via the `tags` argument when that tag is not found in the model.

It is an error to call `check_data_names` when no parameters have been tagged in the model specification file (see `param_tags()`).

Value

A logical value is returned; `TRUE` if all expected parameters were found and `FALSE` otherwise.

See Also

`param_tags()`

Examples

```
mod <- mcode("ex-cdn", "$PARAM @input \n CL = 1, KA = 2", compile = FALSE)

param(mod)

# Coding mistake!
data <- expand.evd(amt = 100, cl = 2, KA = 5)

check_data_names(data, mod)

try(check_data_names(data, mod, mode = "error"))

check_data_names(data, mod, mode = "inform")
```

---

cmtn *Get the compartment number from a compartment name*

Description

Get the compartment number from a compartment name

Usage

```
cmtn(x, ...)

## S4 method for signature 'mrgmod'
cmtn(x, tag, ...)
```

Arguments

`x`	model object.
`...`	not used.
`tag`	compartment name.

Examples

```
mod <- mrgsolve::house()
cmtn(mod, "CENT")
```

---

code *Extract the code from a model*

Description

This function is currently not exported, so be sure to call it with `mrgsolve:::code(...)`.

Usage

```
code(x)
```

Arguments

x	a model object.

Value

A character vector of model code.

Examples

```
mod <- mrgsolve::house()
mrgsolve:::code(mod)

# Alternative
as.list(mod)$code
```

---

collapse_matrix *Collapse the matrices of a matlist object*

Description

This function is called by `collapse_omega()` and `collapse_sigma()` to convert multiple matrix blocks into a single matrix block. This "collapsing" of the matrix list is irreversible.

Usage

```
collapse_matrix(x, range = NULL, name = NULL)
```

Arguments

x	an object that inherits from matlist; this object is most frequently extracted from a model object using omat() or smat() for OMEGA and SIGMA, respectively.
range	numeric vector of length 2 specifying the range of matrices to collapse in case there are more than 2. The second element may be NA to indicate the length of the list of matrices.
name	a new name for the collapsed matrix; note that this is the matrix name, not the labels which alias ETA(n) or EPS(n); specifying a name will only alter how this matrix is potentially updated in the future.

Value

An update matlist object (either omegalist or sigmalist).

See Also

collapse_omega(), collapse_sigma(), omat(), smat()

Examples

```
omega <- omat(list(dmat(1, 2), dmat(3, 4, 5)))
omega
collapse_matrix(omega)
```

---

collapse_omega *Collapse OMEGA or SIGMA matrix lists*

Description

If multiple OMEGA (or SIGMA) blocks were written into the model, these can be collapsed into a single matrix. This will not change the functionality of the model, but will alter how OMEGA (or SIGMA) are updated, usually making it easier. This "collapsing" of the matrix list is irreversible.

Usage

```
collapse_omega(x, range = NULL, name = NULL)

collapse_sigma(x, range = NULL, name = NULL)
```

Arguments

x	a model object.
range	numeric vector of length 2 specifying the range of matrices to collapse in case there are more than 2. The second element may be NA to indicate the length of the list of matrices.

name — a new name for the collapsed matrix; note that this is the matrix name, not the labels which alias ETA(n) or EPS(n); specifying a name will only alter how this matrix is potentially updated in the future.

Value

A model object with updated OMEGA or SIGMA matrix lists.

See Also

collapse_matrix()

Examples

```
code <- '
$OMEGA 1 2 3
$OMEGA 4 5
$OMEGA 6 7 8 9
'

mod <- mcode("collapse-example", code, compile = FALSE)
revar(mod)
collapse_omega(mod) %>% omat()
collapse_omega(mod, range = c(2,3), name = "new_matrix") %>% omat()
collapse_omega(mod, range = c(2,NA), name = "new_matrix") %>% omat()
```

---

custom_tol *Customize tolerances for specific compartments*

Description

These functions update the relative or absolute tolerance values only for the custom tolerance configuration.

Usage

```
custom_tol(.x, .rtol = NULL, .atol = NULL)

custom_rtol(.x, .rtol = list(), .default = NULL, .use = TRUE, ...)

custom_atol(.x, .atol = list(), .default = NULL, .use = TRUE, ...)
```

Arguments

.x — a model object.

.rtol — a named numeric list or vector, where names reference selected model compartments and relative tolerances for those compartments; custom_tol() also accepts the name of an object in the model environment to be used.

.atol	a named numeric list or vector, where names reference selected model compartments and absolute tolerances for those compartments; custom_tol() also accepts the name of an object in the model environment to be used.
.default	the default tolerance value to use for compartments not listed in .rtol, .atol, or ...; if not supplied, the current scalar value in .x will be used.
.use	logical; if TRUE, then a call to use_custom_tol() will be made prior to return; if FALSE, a call to use_scalar_tol() will be made; under expected use, the value for this argument is kept TRUE, so that whenever tolerances are customized, they will be used in the next simulation run.
...	name/value pairs, where name references a model compartment and value is a new, numeric value to use for rtol or atol.

Details

New tolerance values can be supplied by either a named, numeric vector or list via .rtol and .atol or via ... or by both. If duplicate compartment names are found in ... and either .rtol or .atol, the value passed via ... will take precedence.

The custom_tol() function provides a mechanism for coding customized tolerances into the model file itself. Simply create named numeric lists or vectors for customized rtol or atol in a $ENV block. On loading the model, call custom_tol() and supply the names of those objects as .rtol and .atol.

Value

An updated model object.

See Also

reset_tol(), use_custom_tol(), use_scalar_tol(), get_tol()

Examples

```
mod <- house()
mod <- custom_rtol(mod, GUT = 1e-2, CENT = 1e-3)

new_tolerances <- c(GUT = 1e-4, RESP = 1e-5)
mod <- custom_rtol(mod, new_tolerances, RESP = 1e-6)
```

---

data_set *Select a data set for simulation*

Description

The input data set (data_set) is a data frame that specifies observations, model events, and / or parameter values for a population of individuals.

Usage

```
data_set(x, data, ...)

## S4 method for signature 'mrgmod,data.frame'
data_set(x, data, ...)

## S4 method for signature 'mrgmod,ANY'
data_set(x, data, ...)

## S4 method for signature 'mrgmod,ev'
data_set(x, data, ...)
```

Arguments

x	a model object.
data	input data set as a data frame.
...	not used.

Details

Input data sets are R data frames that can include columns with any valid name, however columns with selected names are treated specially by mrgsolve and incorporated into the simulation.

ID specifies the subject ID and is required for every input data set.

When columns have the same name as parameters ($PARAM or $INPUT in the model specification file), the values in those columns will be used to update the corresponding parameter as the simulation progresses.

Input data set may include the following columns related to PK dosing events: TIME, CMT, AMT, RATE, II, ADDL, SS. Both ID and TIME are required columns in the input data set unless $PRED is in use. Lower case PK dosing column names including time, cmt, amt, rate, ii, addl, ss are also recognized. However, an error will be generated if a mix of both upper case and lower case columns in this family are found. Use the functions lctran() and uctran() to convert between upper and lower case naming for these data items.

TIME is the observation or event time, CMT is the compartment number (see init()), AMT is the dosing amount, RATE is the infusion rate, II is the dosing interval, ADDL specifies additional doses to administer, and SS is a flag indicating that the system should be advanced to a pharmacokinetic steady state prior to administering the dose. These column names operate similarly to other nonlinear mixed effects modeling software.

EVID is an integer value specifying the ID of an event record. Values include:

- 0: observation
- 1: dose event, either bolus or infusion
- 2: other-type event; in mrgsolve, this functions like an observation record, but a discontinuity is created in the simulation at the time of the event (i.e., the ODE solver will stop and restart at the time of the event)
- 3: reset the system

- 4: reset the system and dose
- 8: replace the amount in a compartment

For all EVID greater than 0 and less than 100, a discontinuity is created in the simulation, as described for EVID 2.

An error will be generated when mrgsolve detects that the data set is not sorted by time within an individual. mrgsolve does **not** allow time to be reset to zero on records where EVID is set to 4 (reset and dose).

Only numeric data can be brought in to the problem. Any non-numeric data columns will be dropped with warning. See numerics_only(), which is used to prepare the data set.

An error will be generated if any parameter columns in the input data set contain missing values (NA). Likewise, and error will be generated if missing values are found in the following columns: ID, time/TIME, rate/RATE.

See exdatasets for several example data sets that are provided by mrgsolve.

See Also

idata_set(), ev(), valid_data_set(), valid_idata_set(), lctran(), uctran().

Examples

```
mod <- house()

data <- expand.ev(ID = seq(3), amt = c(10, 20))

data(extran1)
head(extran1)

mod %>% data_set(extran1) %>% mrgsim()
mod %>% mrgsim(data = extran1)
```

---

design *Set observation designs for the simulation*

Description

This function also allows you to assign different designs to different groups or individuals in a population.

Usage

```
design(x, deslist = list(), descol = character(0), ...)
```

Arguments

x	model object
deslist	a list of tgrid or tgrids objects or numeric vector to be used in place of ...
descol	the idata column name (character) for design assignment
...	not used

Details

This setup requires the use of an idata_set, with individual-level data passed in one ID per row. For each ID, specify a grouping variable in idata (descol). For each unique value of the grouping variable, make one tgrid object and pass them in order as ... or form them into a list and pass as deslist.

You must assign the idata_set before assigning the designs in the command chain (see the example below).

Examples

```
peak <- tgrid(0,6,0.1)
sparse <- tgrid(0,24,6)

des1 <- c(peak,sparse)
des2 <- tgrid(0,72,4)


data <- expand.ev(ID = 1:10, amt=c(100,300))
data$GRP <- data$amt/100

idata <- data[,c("ID", "amt")]

mod <- mrgsolve::house()

mod %>%
  omat(dmat(1,1,1,1)) %>%
  carry_out(GRP) %>%
  idata_set(idata) %>%
  design(list(des1, des2),"amt") %>%
  data_set(data) %>%
  mrgsim() %>%
  plot(RESP~time|GRP)
```

---

details *Extract model details*

Description

Extract model details

Usage

```
details(x, complete = FALSE, values = TRUE, ...)
```

Arguments

x	a model object
complete	logical; if TRUE, un-annotated parameters and compartments will be added to the output
values	logical; if TRUE, a values column will be added to the output
...	not used

Details

This function is not exported. You will have to call it with `mrgsolve:::details()`.

Examples

```
mod <- mrgsolve::house()

mrgsolve:::details(mod)
```

---

dsl_preprocess *DSL preprocessing functions*

Description

These functions preprocess model code written in the mrgsolve DSL before C++ compilation.

Usage

```
convert_pow(x, block = "")

warn_int_div(x, block = "")

convert_fort_if(x)

convert_semicolons(x)
```

Arguments

x	character vector of source lines to process.
block	model block name; included in warning messages when called during model parsing.

Details

- `convert_pow()`: converts Fortran-style exponentiation (`**`) to C++ `pow()` calls; runs by default unless turned off by environment variable; lines of code will pass through unaltered if `**` is not found.
- `warn_int_div()`: warns about literal integer division (e.g. `3/4`, `1/2`) that truncates toward zero in C++; returns `x` invisibly and is called for its side-effect warnings; runs by default unless turned off by environment variable.
- `convert_fort_if()`: converts Fortran `IF/THEN/ELSE/ENDIF` constructs and relational operators (`.GE.`, `.LE.`, etc.) to C++; runs only when the `nm-vars` plugin is invoked.
- `convert_semicolons()`: appends semicolons to statement lines that are missing them; lines ending with an operator (e.g., `+` or `/` or "=") will not be terminated with a semicolon; this preprocessor must be enlisted through the `semicolons` plugin and it only runs with `nm-vars`; the `semicolons` plugin is brought online when the `nm-like` composite plugin (`nm-vars`, `autodec`, `semicolons`) is invoked.

Processing is controlled by environment variables:

- `MRGSOLVE_CONVERT_POW` (default `TRUE`)
- `MRGSOLVE_CONVERT_FORT_IF` (default `TRUE`)
- `MRGSOLVE_WARN_INT_DIV` (default `TRUE`)

Set any variable to `FALSE` to disable the corresponding step when processing a model file via `mread()`. Adding `semicolons` must be opted into through the `semicolons` or `nm-like` plugins.

Examples

```
convert_pow("a**2")
convert_pow("(WT/70) ** THETA(3)")

code <- c("IF ( WT .GE.90) THEN", "  CL = CL * 0.8", "ENDIF")
cat(code, sep = "\n")
cat(convert_fort_if(code), sep = "\n")

convert_semicolons("CL = THETA1")

code <- c("CL =", "THETA1 *", "(WT/70) *", "exp(ETA(1))")
cat(code, sep = "\n")
cat(convert_semicolons(code), sep = "\n")

warn_int_div("THETA(1) * pow(WT/70, 3/4)")
warn_int_div("3.0/4")
```

env_eval *Re-evaluate the code in the ENV block*

Description

The $ENV block is a block of R code that can realize any sort of R object that might be used in running a model.

Usage

```
env_eval(x, seed = NULL)
```

Arguments

x	a model object.
seed	passed to set.seed() if a numeric value is supplied.

See Also

env_get(), env_get_env(), env_ls()

env_get *Return model environment or objects from the model environment*

Description

Call env_get() passing either a model object or simulated output and name an object to retrieve from the model object environment. env_get_obj() is an alias to env_get(). Call env_get_env() to return the environment itself. Methods for mrgmod and mrgsims both interact with the same environment (see **Examples**).

Usage

```
env_get(x, ...)

## S3 method for class 'mrgmod'
env_get(x, what, ...)

## S3 method for class 'mrgsims'
env_get(x, ...)

env_get_obj(x, ...)

env_get_env(x, ...)
```

```
## S3 method for class 'mrgmod'
env_get_env(x, ...)

## S3 method for class 'mrgsims'
env_get_env(x, ...)
```

Arguments

x	a model object (class mrgmod) or simulated output (class mrgsims).
...	passed base::get().
what	the name of an object to return.

Examples

```
mod <- house(end = 1)

# Just for the example
assign("let", letters[1:3], env_get_env(mod))

out <- mrgsim(mod)

env_get(out, "let")

env_get(mod, "let")

env_get_obj(out, "let")

env_get_env(mod)

# It's the same environment in out that is in mod
env_get_env(out)
```

---

env_ls *List objects in the model environment*

Description

Each model keeps an internal environment that allows the user to carry any R object along. Objects are coded in $ENV.

Usage

```
env_ls(x, ...)
```

Arguments

x	a model object.
...	passed to ls().

env_update *Update objects in model environment*

Description

Update objects in model environment

Usage

```
env_update(.x, ..., .dots = list())
```

Arguments

.x	a model object.
...	objects to update.
.dots	list of objects to updated.

ev *Event objects for simulating PK and other interventions*

Description

An event object specifies dosing or other interventions that get implemented during simulation. Event objects do similar things as data_set, but simpler and easier to create.

Usage

```
ev(x, ...)

## S4 method for signature 'mrgmod'
ev(x, object = NULL, ...)

## S4 method for signature 'missing'
ev(
  time = 0,
  amt = 0,
  evid = 1,
  cmt = 1,
  ID = numeric(0),
  replicate = TRUE,
  until = NULL,
  tinf = NULL,
  realize_addl = FALSE,
  ...
)
```

```
## S4 method for signature 'ev'
ev(x, realize_addl = FALSE, ...)
```

Arguments

x	a model object.
...	other items to be incorporated into the event object; see **Details**.
object	an event object to be added to a model object.
time	event time.
amt	dose amount.
evid	event ID.
cmt	compartment number or name.
ID	subject ID.
replicate	logical; if TRUE, events will be replicated for each individual in ID.
until	the expected maximum **observation** time for this regimen; doses will be scheduled up to, but not including, the until time; see **Examples**.
tinf	infusion time; if greater than zero, then the rate item will be derived as amt/tinf.
realize_addl	if FALSE (default), no change to addl doses. If TRUE, addl doses are made explicit with realize_addl().

Details

- Required items in events objects include time, amt, evid and cmt.
- If not supplied, evid is assumed to be 1.
- If not supplied, cmt is assumed to be 1.
- If not supplied, time is assumed to be 0.
- If amt is not supplied, an error will be generated.
- If total is supplied, then addl will be set to total-1.
- Other items can include ii, ss, and addl (see data_set for details on all of these items).
- ID may be specified as a vector.
- If replicate is TRUE (default), then the events regimen is replicated for each ID; otherwise, the number of event rows must match the number of IDs entered.

Value

ev() returns an event object.

See Also

evd(), ev_rep(), ev_days(), ev_repeat(), ev_assign(), ev_seq(), mutate.ev(), as.ev(), as.evd(), ev_methods.

Examples

```
mod <- mrgsolve::house()

mod <- mod %>% ev(amt = 1000, time = 0, cmt = 1)

loading <- ev(time = 0, cmt = 1, amt = 1000)

maint <- ev(time = 12, cmt = 1, amt = 500, ii = 12, addl = 10)

c(loading, maint)

reduced_load <- dplyr::mutate(loading, amt = 750)

# Three additional doses in this case
e <- ev(amt = 100, ii = 4*7, until = 16*7)
e
# Last dose is given at 84
realize_addl(e)

# Four additional doses with last at 112 in this case
e <- ev(amt = 100, ii = 4*7, until = 16*7 + 0.001)
realize_addl(e)
```

---

ev_assign *Replicate a list of events into a data set*

Description

Replicate a list of events into a data set

Usage

```
ev_assign(l, idata, evgroup, join = FALSE)

assign_ev(...)
```

Arguments

l	list of event objects.
idata	an idata set (one ID per row).
evgroup	the character name of the column in idata that specifies event object to implement.
join	if TRUE, join idata to the data set before returning.
...	used to pass arguments from assign_ev(). to ev_assign().

Details

`ev_assign()` connects events in a list passed in as the `l` argument to values in the data set identified in the `evgroup` argument. For making assignments, the unique values in the `evgroup` column are first sorted so that the first sorted unique value in `evgroup` is assigned to the first event in `l`, the second sorted value in `evgroup` column is assigned to the second event in `l`, and so on. This is a change from previous behavior, which did not sort the unique values in `evgroup` prior to making the assignments.

Examples

```
ev1 <- ev(amt = 100)
ev2 <- ev(amt = 300, rate = 100, ii = 12, addl = 10)

idata <- data.frame(ID = seq(10))
idata$arm <- 1+(idata$ID %%2)

ev_assign(list(ev1, ev2), idata, "arm", join = TRUE)
```

---

ev_days *Schedule dosing events on days of the week*

Description

This function lets you schedule doses on specific days of the week, allowing you to create dosing regimens on Monday/Wednesday/Friday, or Tuesday/Thursday, or every other day (however you want to define that) etc.

Usage

```
ev_days(
  ev = NULL,
  days = "",
  addl = 0,
  ii = 168,
  unit = c("hours", "days"),
  ...
)
```

Arguments

`ev`	an event object.
`days`	comma- or space-separated character string of valid days of the the week (see details).
`addl`	additional doses to administer.
`ii`	inter-dose interval; intended use is to keep this at the default value.
`unit`	time unit; the function can only currently handle hours or days.
`...`	event objects named by one of the valid days of the week (see **Details**).

Details

Valid names of the week are:

- `m` for Monday
- `t` for Tuesday
- `w` for Wednesday
- `th` for Thursday
- `f` for Friday
- `sa` for Saturday
- `s` for Sunday

The whole purpose of this function is to schedule doses on specific days of the week, in a repeating weekly schedule. Please do use caution when changing `ii` from its default value.

Examples

```
# Monday, Wednesday, Friday x 4 weeks
e1 <- ev(amt = 100)
ev_days(e1, days="m,w,f", addl = 3)

# 50 mg Tuesdays, 100 mg Thursdays x 6 months
e2 <- ev(amt = 50)
ev_days(t = e2, th = e1, addl = 23)
```

---

ev_rep *Replicate an event object*

Description

An event sequence can be replicated a certain number of times in a certain number of IDs.

Usage

```
ev_rep(x, ID = 1, n = NULL, wait = 0, as.ev = FALSE, id = NULL)
```

Arguments

`x`	event object.
`ID`	numeric vector if IDs.
`n`	passed to `ev_repeat()`.
`wait`	passed to `ev_repeat()`.
`as.ev`	if `TRUE` an event object is returned.
`id`	deprecated; use `ID` instead.

Value

A single data.frame or event object as determined by the value of as.ev().

See Also

ev_repeat()

Examples

```
e1 <- c(ev(amt=100), ev(amt=200, ii=24, addl=2, time=72))

ev_rep(e1, 1:5)
```

---

ev_repeat *Repeat a block of dosing events*

Description

Repeat a block of dosing events

Usage

```
ev_repeat(x, n, wait = 0, as.ev = FALSE)
```

Arguments

x	event object or dosing data frame.
n	number of times to repeat.
wait	time to wait between repeats.
as.ev	if TRUE, an event object is returned; otherwise a data.frame is returned.

Value

See as.ev argument.

Examples

```
e1 <- ev(amt = 100, ii = 24, addl = 20)
e4 <- ev_repeat(e1, n = 4, wait = 168)
mod <- mrgsolve::house()
out <- mrgsim(mod, events = e4, end = 3200)
plot(out, "CP")
```

ev_rx *Create intervention objects from Rx input*

Description

See details below for Rx specification. Actual parsing is done by `parse_rx()`; this function can be used to debug Rx inputs.

Usage

```
ev_rx(x, y, ...)

## S4 method for signature 'mrgmod,character'
ev_rx(x, y, ...)

## S4 method for signature 'character,missing'
ev_rx(x, df = FALSE, ...)

parse_rx(x)
```

Arguments

x	a model object or `character` Rx input.
y	`character` Rx input; see details.
...	not used at this time.
df	if `TRUE` then a data frame is returned.

Value

The method dispatched on model object (`mrgmod`) returns another model object. The `character` method returns an event object. The `parse_rx` function return a list named with arguments for the event object constructor `ev()`.

Rx specification

- The dose is found at the start of the string by sequential digits; this may be integer, decimal, or specified in scientific notation
- Use `in` to identify the dosing compartment number; must be integer
- Use `q` to identify the dosing interval; must be integer or decimal number (but not scientific notation)
- Use `over` to indicate an infusion and its duration; integer or decimal number
- Use `x` to indicate total number of doses; must be integer
- Use `then` or `,` to separate dosing periods
- Use `after` to insert a lag in the start of a period; integer or decimal number (but not scientific notation)
- Use `&` to implement multiple doses at the same time

Examples

```
# example("ev_rx")

ev_rx("100")

ev_rx("100 in 2")

ev_rx("100 q12 x 3")

ev_rx("100 over 2")

ev_rx("100 q 24 x 3 then 50 q12 x 2")

ev_rx("100 then 50 q 24 after 12")

ev_rx("100.2E-2 q4")

ev_rx("100 over 2.23")

ev_rx("100 q 12 x 3")

ev_rx("100 in 1 & 200 in 2")

parse_rx("100 mg q 24 then 200 mg q12")
```

---

ev_seq *Schedule a series of event objects*

Description

Use this function when you want to schedule two or more event objects in time according the dosing interval (`ii`) and additional doses (`addl`).

Usage

```
ev_seq(..., ID = NULL, .dots = NULL, id = NULL)

## S3 method for class 'ev'
seq(...)
```

Arguments

`...`	event objects or numeric arguments named `wait` or `ii` to implement a period of no-dosing activity in the sequence (see **Details**).
`ID`	numeric vector of subject IDs.
`.dots`	a list of event objects that replaces `....`
`id`	deprecated; use `ID`.

Details

Use the generic `seq()` when the first argument is an event object. If a waiting period (`wait` or `ii`) is the first event, you will need to use `ev_seq()`. When an event object has multiple rows, the end time for that sequence is taken to be one dosing interval after the event that takes place on the last row of the event object.

The doses for the next event line start after all of the doses from the previous event line plus one dosing interval from the previous event line (see **Examples**).

When numerics named `wait` or `ii` are mixed in with the event objects, a period with no dosing activity is incorporated into the sequence, between the adjacent dosing event objects. `wait` and `ii` accomplish a similar result, but differ by the starting point for the inactive period.

- Use `wait` to schedule the next dose relative to the end of the dosing interval for the previous dose.
- Use `ii` to schedule the next dose relative to the time of the the previous dose.

So `wait` acts like similar to an event object, by starting the waiting period from one dosing interval after the last dose while `ii` starts the waiting period from the time of the last dose itself. Both `wait` and `ii` can accomplish identical behavior depending on whether the last dosing interval is included (or not) in the value. Values for `wait` or `ii` can be negative.

NOTE: `.ii` had been available historically as an undocumented feature. Starting with mrgsolve version `0.11.3`, the argument will be called `ii`. For now, both `ii` and `.ii` will be accepted but you will get a deprecation warning if you use `.ii`. Please use `ii` instead.

Values for `time` in any event object act like a prefix time spacer wherever that event occurs in the event sequence (see **Examples**).

Value

A single event object sorted by `time`.

Examples

```
e1 <- ev(amt = 100, ii = 12, addl = 1)

e2 <- ev(amt = 200)

seq(e1, e2)

seq(e1, ii = 8, e2)

seq(e1, wait = 8, e2)

seq(e1, ii = 8, e2, ID = seq(10))

ev_seq(ii = 12, e1, ii = 120, e2, ii = 120, e1)

seq(ev(amt = 100, ii = 12), ev(time = 8, amt = 200))
```

evd *Create an event object with data-like names*

Description

This function calls `ev()` to create an event object and then sets the case attribute so that it renders nmtran data names in upper case. An object created with `evd()` can be used in the same way as an object created with `ev()`.

Usage

```
evd(x, ...)

## S4 method for signature 'mrgmod'
evd(x, ...)

## S4 method for signature 'missing'
evd(x, ...)

## S4 method for signature 'ev'
evd(x, ...)

as.evd(x)
```

Arguments

x	an event object.
...	arguments passed to `ev()`.

Details

Note that `evd` isn't a separate class; it is just an `ev` object with a specific `case` attribute. See examples which illustrate the difference.

See Also

`ev()`, `lctran()`, `uctran()`

Examples

```
a <- evd(amt = 100)
b <- ev(amt = 300)
a
as.data.frame(a)
as_data_set(a, b)
as_data_set(b, a)
as.data.frame(seq(a, b))
```

exdatasets *Example input data sets*

Description

Example input data sets

Usage

```
data(exidata)

data(extran1)

data(extran2)

data(extran3)

data(exTheoph)

data(exBoot)
```

Details

- exidata holds individual-level parameters and other data items, one per row
- extran1 is a "condensed" data set
- extran2 is a full dataset
- extran3 is a full dataset with parameters
- exTheoph is the theophylline data set, ready for input into mrgsolve
- exBoot a set of bootstrap parameter estimates

Examples

```
mod <- mrgsolve::house() %>% update(end=240) %>% Req(CP)

## Full data set
data(exTheoph)
out <- mod %>% data_set(exTheoph) %>% mrgsim
out
plot(out)

## Condensed: mrgsolve fills in the observations
data(extran1)
out <- mod %>% data_set(extran1) %>% mrgsim
out
plot(out)

## Add a parameter to the data set
```

```
stopifnot(require(dplyr))
data <- extran1 %>% distinct(ID) %>% select(ID) %>%
  mutate(CL=exp(log(1.5) + rnorm(nrow(.), 0,sqrt(0.1)))) %>%
  left_join(extran1,.)

data

out <- mod %>% data_set(data) %>% carry_out(CL) %>%  mrgsim
out
plot(out)

## idata
data(exidata)
out <- mod %>% idata_set(exidata) %>% ev(amt=100,ii=24,addl=10) %>% mrgsim
plot(out, CP~time|ID)
```

`expand.idata` *Create template data sets for simulation*

Description

These functions expand all combinations of arguments using `expand.grid()`. `expand.idata()` generates an `idata` set; the others generate a full data set. The result always has only one row for one individual. Use `expand.evd()` or `evd_expand()` to render NMTRAN names (e.g. `AMT` or `CMT`) in upper case.

Usage

```
expand.idata(...)

expand.ev(...)

expand.evd(...)

ev_expand(...)

evd_expand(...)
```

Arguments

`...`	passed to `expand.grid()`.

Details

An ID column is added as if not supplied by the user. In the output data frame, ID is always re-written as the row number.

For `expand.ev()`, defaults also added include `cmt = 1`, `time = 0`, `evid = 1`. If `total` is included, then `addl` is derived as `total-1`. If `tinf` is included, then an infusion rate is derived for row where `tinf` is greater than zero.

ev_expand() is a synonym for expand.ev() and evd_expand() is a synonym for expand.evd().

Value

A data frame containing one row for each combination of the items passed in .... The result always has ID set to the row number.

Examples

```
idata <- expand.idata(CL = c(1,2,3), VC = c(10,20,30))

doses <- expand.ev(amt = c(300,100), ii = c(12,24), cmt = 1)

infusion <- expand.ev(amt = 100, tinf = 2)
```

---

expand_observations *Insert observations into a data set*

Description

Insert observations into a data set

Usage

```
expand_observations(data, times, unique = FALSE, obs_pos = -1L)
```

Arguments

data	a data set or event object.
times	a vector of observation times.
unique	logical; if TRUE then values for time are dropped if they are found anywhere in data.
obs_pos	determines sorting order for observations; use -1 (default) to put observations first; otherwise, use large integer to ensure observations are placed after doses.

Details

Non-numeric columns will be dropped with a warning.

Value

A data frame with additional rows for added observation records.

Examples

```
data <- expand.ev(amt = c(100, 200, 300))

expand_observations(data, times = seq(0, 48, 2))
```

get_tol *Extract rtol and atol information from a model object*

Description

Extract rtol and atol information from a model object

Usage

```
get_tol(x)

get_tol_list(x)
```

Arguments

x	a model object.

Value

A data frame (`get_tol()`) or a named list (`get_tol_list()`).

See Also

`reset_tol()`, `custom_tol()`, `use_custom_tol()`, `use_scalar_tol()`

Examples

```
mod <- house()
get_tol(mod)
get_tol_list(mod)
```

idata_set *Select a idata set for simulation*

Description

The individual data set (`idata_set`) is a data frame with one row for each individual in a population, specifying parameters and other individual-level data.

Usage

```
idata_set(x, data, ...)

## S4 method for signature 'mrgmod,data.frame'
idata_set(x, data, ...)

## S4 method for signature 'mrgmod,ANY'
idata_set(x, data, ...)
```

Arguments

x	model object.
data	a data set that can be coerced to data.frame.
...	not used; idata_set() accepts no other arguments.

Details

The idata_set is a data frame that specifies individual-level data for the problem. An ID column is required and there can be no more than one row in the data frame for each individual.

In most cases, the columns in the idata_set have the same names as parameters in the param() list. When this is the case, the parameter set is updated as the simulation proceeds once at the start of each individual. The idata_set can also be used to set initial conditions for each individual: for a compartment called CMT, make a column in idata_set called CMT_0 and make the value the desired initial value for that compartment. Note that this initial condition will be overridden if you also set the CMT_0 in $MAIN ($PK).

The most common application of idata_set is to specify a population or batch of simulations to do. We commonly use idata_set with an event object (see ev()). In that case, the event gets applied to each individual in the idata_set.

It is also possible to provide both a data_set and a idata_set. In this case, the idata_set is used as a parameter lookup for IDs found in the data_set. Remember in this case, it is the data_set (not the idata_set) that determines the number of individuals in the simulation.

An error will be generated if any parameter columns in the input idata set contain NA.

See Also

data_set(), ev()

Examples

```
mod <- house()

data(exidata)

exidata

mod %>%
  idata_set(exidata) %>%
  ev(amt = 100) %>%
  mrgsim()

mod %>% ev(amt = 100) %>% mrgsim(idata = exidata)
```

`init` *Methods for working with the model compartment list*

Description

Calling `init()` with the model object as the first argument will return the model initial conditions as a numericlist object. See numericlist for methods to deal with `cmt_list` objects.

Usage

```
init(.x, ...)

## S4 method for signature 'mrgmod'
init(.x, .y = list(), ..., .pat = "*")

## S4 method for signature 'mrgsims'
init(.x, ...)

## S4 method for signature 'missing'
init(.x, ...)

## S4 method for signature 'list'
init(.x, ...)

## S4 method for signature 'ANY'
init(.x, ...)
```

Arguments

`.x`	the model object.
`...`	`name = value` assignments to update the initial conditions list.
`.y`	list to be merged into parameter list.
`.pat`	a regular expression (character) to be applied as a filter when printing compartments to the screen.

Details

Can be used to either get a compartment list object from a `mrgmod` model object or to update the compartment initial conditions in a model object. For both uses, the return value is a `cmt_list` object. For the former use, `init()` is usually called to print the compartment initial conditions to the screen, but the `cmt_list` object can also be coerced to a list or numeric R object.

Value

An object of class `cmt_list` (see numericlist).

Examples

```
## example("init")
mod <- mrgsolve::house()

init(mod)

init(mod, .pat="^C") ## may be useful for large models

class(init(mod))

init(mod)$CENT

as.list(init(mod))

as.data.frame(init(mod))
```

`inventory` *Check whether all required parameters needed in a model are present in an object*

Description

This function has largely been superseded by `check_data_names()`.

Usage

```
inventory(x, obj, ..., .strict = FALSE)
```

Arguments

`x`	model object.
`obj`	data.frame to pass to `idata_set()` or `data_set()`.
`...`	capture dplyr-style parameter requirements.
`.strict`	whether to stop execution if all requirements are present (`TRUE`) or just warn (`FALSE`); see **Details**.

Details

If parameter requirements are not explicitly stated, the requirement defaults to all parameter names in `x`. Note that, by default, the inventory is not `.strict` unless the user explicitly states the parameter requirement. That is, if parameter requirements are explicitly stated, `.strict` will be set to `TRUE` if a value `.strict` was not passed in the call.

Value

`x` is returned invisibly.

See Also

check_data_names()

Examples

```
## Not run:
  inventory(mod, idata, CL:V) # parameters defined, inclusively, CL through Volume
  inventory(mod, idata, everything()) # all parameters
  inventory(mod, idata, contains("OCC")) # all parameters containing OCC
  inventory(mod, idata, -F) # all parameters except F

## End(Not run)
```

---

is.mrgmod *Check if an object is a model object*

Description

The function checks to see if the object is either mrgmod or packmod.

Usage

```
is.mrgmod(x)
```

Arguments

x	any object

Value

TRUE if the object inherits from either mrgmod or packmod class.

Examples

```
mod <- mrgsolve::house()
is.mrgmod(mod)
```

is.mrgsims *Check if an object is mrgsims output*

Description

Check if an object is mrgsims output

Usage

```
is.mrgsims(x)
```

Arguments

x	any object.

Value

TRUE if x inherits mrgsims.

knobs *DEFUNCT: Run sensitivity analysis on model settings*

Description

Try the 'mrgsim.sa' package instead.

Usage

```
knobs(...)
```

Arguments

...	not used.

lctran *Change the case of nmtran-like data items*

Description

Previous data set requirements included lower case names for data items like AMT and EVID. Lower case is no longer required. However, it is still a requirement that nmtran like data column names are either all lower case or all upper case.

Usage

```
lctran(data, ...)

## S3 method for class 'data.frame'
lctran(data, warn = TRUE, ...)

## S3 method for class 'ev'
lctran(data, ...)

uctran(data, ...)

## S3 method for class 'data.frame'
uctran(data, warn = TRUE, ...)

## S3 method for class 'ev'
uctran(data, ...)
```

Arguments

data	a data set with nmtran-like format or an event object.
...	for potential future use.
warn	if TRUE, a warning will be issued when there are both upper and lower case versions of any nmtran-like column in the data frame.

Details

Columns that will be renamed with lower or upper case versions:

- AMT / amt
- II / ii
- SS / ss
- CMT / cmt
- ADDL / addl
- RATE / rate
- EVID / evid

- TIME / time

If both lower and upper case versions of the name are present in the data frame, no changes will be made.

Value

A data frame or event object, with column names possibly converted to upper or lower case.

Examples

```
data <- data.frame(TIME = 0, AMT = 5, II = 24, addl = 2, WT = 80)
lctran(data)

data <- data.frame(TIME = 0, AMT = 5, II = 24, addl = 2, wt = 80)
uctran(data)

ev <- evd(amt = 100, evid = 3)
uctran(ev)

# warning
data <- data.frame(TIME = 1, time = 2, CMT = 5)
lctran(data)
```

---

loadso *Load the model shared object*

Description

Once the model is compiled, the model object can be used to re-load the model shared object (the compiled code underlying the mode) when the simulation is to be done in a different R process.

Usage

```
loadso(x, ...)

## S3 method for class 'mrgmod'
loadso(x, ...)
```

Arguments

x	a model object.
...	not used.

Details

The loadso function most frequently needs to be used when parallelizing simulations across worker nodes. The model can be run after calling loadso, without requiring that it is re-compiled on worker nodes. It is likely required that the model is built (and the shared object stored) in a local directory off of the working R directory (see the second example).

Value

The model object (invisibly).

Examples

```
## Not run:
  mod <- mread("pk1", modlib())
  loadso(mod)

  mod2 <- mread("pk2", modlib(), soloc = "build")
  loadso(mod2)

## End(Not run)
```

`matrix_helpers` *Create matrices from vector input*

Description

These functions are simple utilities for creating diagonal, block or correlation matrices.

Usage

```
bmat(..., correlation = FALSE, digits = -1)

cmat(..., digits = -1)

dmat(...)
```

Arguments

`...`	matrix data.
`correlation`	logical; if `TRUE`, off-diagonal elements are assumed to be correlations and converted to covariances.
`digits`	if greater than zero, matrix is passed to `signif()` (along with digits) prior to returning.

Details

`bmat()` makes a block matrix. `cmat()` makes a correlation matrix. `dmat()` makes a diagonal matrix.

Value

A matrix.

See Also

as_bmat(), as_dmat()

Examples

```
dmat(1,2,3)/10

bmat(0.5,0.01,0.2)

cmat(0.5, 0.87,0.2)
```

---

mcode *Write, compile, and load model code*

Description

This is a convenience function that ultimately calls mread(). Model code is written to a file and read back in using mread().

Usage

```
mcode(model, code, project = getOption("mrgsolve.project", tempdir()), ...)

mcode_cache(
  model,
  code,
  project = getOption("mrgsolve.project", tempdir()),
  ...
)
```

Arguments

model	model name.
code	character string specifying a mrgsolve model.
project	project directory for the model.
...	passed to mread(); see that help topic for other arguments that can be set.

Details

Note that the arguments are in slightly different order than mread(). The default project is tempdir().

See the mread() help topic for discussion about caching compilation results with mcode_cache().

See Also

mread(), mread_cache()

Examples

```
## Not run:
code <- '
$CMT DEPOT CENT
$PKMODEL ncmt=1, depot=TRUE
$MAIN
double CL = 1;
double V = 20;
double KA = 1;
'

mod <- mcode("example", code, compile = FALSE)

## End(Not run)
```

---

mcRNG *Set RNG to use L'Ecuyer-CMRG*

Description

Set RNG to use L'Ecuyer-CMRG

Usage

```
mcRNG()
```

---

modlib *Internal model library*

Description

Pre-coded models are included in the mrgsolve installation; these can be compiled and loaded with `modlib()`. These models are usually most useful for exploratory simulation or learning mrgsolve. Production simulation work is typically accomplished by a custom-coded model.

Usage

```
modlib(model = NULL, ..., list = FALSE)
```

Arguments

`model`	`character` name of a model in the library.
`...`	passed to `mread_cache()`.
`list`	logical; if `TRUE`, a list of available models is returned.

Details

See modlib_details, modlib_pk, modlib_pkpd, modlib_tmdd, modlib_viral for details.

Call `modlib("<modelname>")` to compile and load a mode from the library.

Call `modlib(list=TRUE)` to list available models. Once the model is loaded (see examples below), call `as.list(mod)$code` to extract model code and equations.

Examples

```
## Not run:
mod <- mread("pk1cmt", modlib())
mod <- mread("pk2cmt", modlib())
mod <- mread("pk3cmt", modlib())
mod <- mread("pk1",    modlib())
mod <- mread("pk2",    modlib())
mod <- mread("pk3",    modlib())
mod <- mread("popex",  modlib())
mod <- mread("irm1",   modlib())
mod <- mread("irm2",   modlib())
mod <- mread("irm3",   modlib())
mod <- mread("irm4",   modlib())
mod <- mread("emax",   modlib())
mod <- mread("effect", modlib())
mod <- mread("tmdd",   modlib())
mod <- mread("viral1", modlib())
mod <- mread("viral2", modlib())
mod <- mread("pred1",  modlib())
mod <- mread("pbpk",   modlib())
mod <- mread("1005",   modlib())  # embedded NONMEM result
mod <- mread("nm-like", modlib()) # model with nonmem-like syntax
mod <- mread("evtools", modlib())

as.list(mod)$code

## End(Not run)
```

---

modlib_details *modlib: PK/PD Model parameters, compartments, and output variables*

Description

modlib: PK/PD Model parameters, compartments, and output variables

Compartments

- `EV`, `EV2`: extravascular dosing compartments
- `CENT`: central PK compartment
- `PERIPH`: peripheral PK compartment

- PERIPH2: peripheral PK compartment 2
- RESP: response PD compartment (irm models)

Output variables

- CP: concentration in the central compartment
- RESP: response (emax model)

PK parameters

- KA, KA2: first order absorption rate constants from first and second extravascular compartment (1/time)
- CL: clearance (volume/time)
- V: volume of distribution (volume)
- V2: volume of distribution, central compartment (volume)
- V3: volume of distribution, peripheral compartment (volume)
- V4: volume of distribution, peripheral compartment 2 (volume)
- Q: intercompartmental clearance (volume/time)
- Q3: intercompartmental clearance (volume/time)
- Q4: intercompartmental clearance 2 (volume/time)
- VMAX: maximum rate, nonlinear process (mass/time)
- KM: Michaelis constant (mass/volume)
- K10: elimination rate constant (1/time)
- K12: rate constant for transfer to peripheral compartment from central (1/time)
- K21: rate constant for transfer to central compartment from peripheral (1/time)

PD parameters

- E0: baseline effect (emax model)
- EMAX, IMAX: maximum effect (response)
- EC50, IC50: concentration producing 50 percent of effect (mass/volume)
- KIN: zero-order response production rate (irm models) (response/time)
- KOUT: first-order response elimination rate (irm models) (1/time)
- n: sigmoidicity factor
- KEO: rate constant for transfer to effect compartment (1/time)

`modlib_pk` *modlib: Pharmacokinetic models*

Description

modlib: Pharmacokinetic models

Arguments

...	passed to update.

Details

See modlib_details for more detailed descriptions of parameters and compartments.

The `pk1cmt` model is parameterized in terms of `CL`, `V`, `KA` and `KA2` and uses compartments `EV`, `EV2`, and `CENT`. The `pk2cmt` model adds a `PERIPH` compartment and parameters `Q` and `V3` to that of the one-compartment model. Likewise, the three-compartment model (`pk3cmt`) adds `PERIPH2` and parameters `Q4` and `V4` to that of the two-compartment models. All pk models also have parameters `VMAX` (defaulting to zero, no non-linear clearance) and `KM`.

Model description

All ODE-based pk models have two extravascular dosing compartments and potential for linear and nonlinear clearance.

- `pk1cmt`: one compartment pk model using ODEs
- `pk2cmt`: two compartment pk model using ODEs
- `pk3cmt`: three compartment pk model using ODEs
- `pk1`: one compartment pk model in closed-form
- `pk2`: two compartment pk model in closed-form
- `pk3`: three compartment pk model in closed-form
- `popex`: a simple population pk model

`modlib_pkpd` *modlib: Pharmacokinetic / pharmacodynamic models*

Description

modlib: Pharmacokinetic / pharmacodynamic models

Details

See modlib_details for more detailed descriptions of parameters and compartments.

All PK/PD models include 2-compartment PK model with absorption from 2 extravascular compartments and linear + nonlinear clearance. The PK models are parameterized with CL, V2, Q, V3, VMAX, KM, KAandKA2and implement compartmentsEV, EV2, CENT, PERIPH. The indirect response mo

Also, once the model is loaded, use the see() method for mrgmod to view the model code.

Model description

- irm1: inhibition of response production
- irm2: inhibition of response loss
- irm3: stimulation of response production
- irm4: stimulation of response loss
- pd_effect: effect compartment model
- emax: sigmoid emax model

---

modlib_tmdd *modlib: Target mediated disposition model*

Description

modlib: Target mediated disposition model

Arguments

...	passed to update.

Parameters

- KEL: elimination rate constant
- KTP: tissue to plasma rate constant
- KPT: plasma to tissue rate constant
- V2: volume of distribution
- KA, KA2: absorption rate constants
- KINT: internalization rate constant
- KON: association rate constant
- KOFF: dissociation rate constant
- KSYN: target synthesis rate
- KDEG: target degradation rate constant

Compartments

- CENT: unbound drug in central compartment
- TISS: unbound drug in tissue compartment
- REC: concentration of target
- RC: concentration of drug-target complex
- EV, EV2: extravascular dosing compartments

Output variables

- CP: unbound drug in the central compartment
- TOTAL: total concentration of target (complexed and uncomplexed)

---

modlib_viral *modlib: HCV viral dynamics models*

Description

modlib: HCV viral dynamics models

Models

- viral1: viral dynamics model with single HCV species
- viral2: viral dynamics model with wild-type and mutant HCV species

Parameters

- s: new hepatocyte synthesis rate (cells/ml/day)
- d: hepatocyte death rate constant (1/day)
- p: viral production rate constant (copies/cell/day)
- beta: new infection rate constant (ml/copy/day)
- delta: infected cell death rate constant (1/day)
- c: viral clearance rate constant (1/day)
- fit: mutant virus fitness
- N: non-target hepatocytes
- mu: forward mutation rate
- Tmax: maximum number of target hepatocytes (cells/ml)
- rho: maximum hepatocyte regeneration rate (1/day)

Compartments

- T: uninfected target hepatocytes (cells/ml)
- I: productively infected hepatocytes (cells/ml)
- V: hepatitis C virus (copies/ml)
- IM: mutant infected hepatocytes (cells/ml)
- VM: mutant hepatitis C virus (copies/ml)
- expos: exposure metric to drive pharmacodynamic model

---

mread *Read a model specification file*

Description

mread() reads and parses the mrgsolve model specification file, builds the model, and returns a model object for simulation. mread_cache() does the same, but caches the compilation result for later use. mread_file() can be used for convenience, taking the model file name as the first argument.

Usage

```
mread(
  model,
  project = getOption("mrgsolve.project", getwd()),
  code = NULL,
  file = NULL,
  udll = TRUE,
  ignore.stdout = TRUE,
  raw = FALSE,
  compile = TRUE,
  audit = TRUE,
  quiet = getOption("mrgsolve_mread_quiet", FALSE),
  check.bounds = FALSE,
  warn = TRUE,
  soloc = getOption("mrgsolve.soloc", tempdir()),
  capture = NULL,
  preclean = FALSE,
  recover = FALSE,
  ...
)

mread_cache(
  model = NULL,
  project = getOption("mrgsolve.project", getwd()),
  file = paste0(model, ".cpp"),
  code = NULL,
```

```
  soloc = getOption("mrgsolve.soloc", tempdir()),
  quiet = FALSE,
  preclean = FALSE,
  capture = NULL,
  ...
)

mread_file(file, ...)
```

Arguments

model	model name.
project	location of the model specification file an any headers to be included; see also the discussion about model; this argument can be set via options(). library under details as well as the modlib() help topic.
code	a character string with model specification code to be used instead of a model file.
file	the full file name (with extension, but without path) where the model is specified.
udll	use unique name for shared object.
ignore.stdout	passed to system call when compiling the model; set this to FALSE to print output to the R console.
raw	if TRUE, return model content as a list, bypassing the compile step; this argument is typically used for debugging problems with the model build.
compile	logical; if TRUE, the model will be built.
audit	check the model specification file for errors.
quiet	don't print messages from mrgsolve when compiling.
check.bounds	check boundaries of parameter list.
warn	logical; if TRUE, print warning messages that may arise while building the model.
soloc	the directory location where the model shared object is built and stored; see details; this argument can be set via options(); if the directory does not exist, mread() will attempt to create it.
capture	a character vector or comma-separated string of additional model variables to capture; these variables will be added to the capture list for the current call to mread() only.
preclean	logical; if TRUE, compilation artifacts are cleaned up first.
recover	if TRUE, a list of build will be returned in case the model shared object fails to compile; use this option to and the returned object to collect information assist in debugging.
...	passed to update(); also arguments passed to mread() from mread_cache().

Details

The model argument is required. For typical use, the file argument is omitted and the value for file is generated from the value for model. To determine the source file name, mrgsolve will look for a file extension in model. A file extension is assumed when it finds a period followed by one to three alpha-numeric characters at the end of the string (e.g. mymodel.txt but not my.model). If no file extension is found, the extension .cpp is assumed (e.g. file is <model-name>.cpp). If a file extension is found, file is <model-name>.

Best practice is to avoid using . in model unless you are using model to point to the model specification file name. Otherwise, use mread_file().

Use the soloc argument to specify a directory location for building the model. This is the location where the model shared object will be stored on disk. The default is a temporary directory, so compilation artifacts are lost when R restarts when the default is used. Changing soloc to a persistent directory location will preserve those artifacts across R restarts. Also, if simulation from a single model is being done in separate processes on separate compute nodes, it might be necessary to store these compilation artifacts in a local directory to make them accessible to the different nodes. If the soloc directory does not exist, mread() will attempt to create it.

Similarly, using mread_cache() will cache results in the temporary directory and the cache cannot be accessed after the R process is restarted.

Model Library

mrgsolve comes bundled with several pre-coded PK, PK/PD, and other systems models that are accessible via the mread() interface.

Models available in the library include:

- PK models: pk1cmt, pk2cmt, pk3cmt, pk1, pk2, popex, tmdd
- PKPD models: irm1, irm2, irm3, irm4, emax, effect
- Other models: viral1, viral2

When the library model is accessed, mrgsolve will compile and load the model as you would for any other model. It is only necessary to reference the correct model name and point the project argument to the mrgsolve model library location via modlib().

For more details, see modlib_pk, modlib_pkpd, modlib_tmdd, modlib_viral, and modlib_details for more information about the state variables and parameters in each model.

See Also

mcode(), mcode_cache()

Examples

```
## Not run:
code <- '
$PARAM CL = 1, VC = 5
$CMT CENT
$ODE dxdt_CENT = -(CL/VC)*CENT;
'
```

```
mod <- mcode("ex_mread", code)
mod

mod %>% init(CENT=1000) %>% mrgsim() %>% plot()

mod <- mread("irm3", modlib())

# if the model is in the file mymodel.cpp
mod <- mread("mymodel")

# if the model is in the file mymodel.txt
mod <- mread(file = "mymodel.txt")

or

mod <- mread_file("mymodel.txt")

## End(Not run)
```

`mread_yaml` *Read a model from yaml format*

Description

Read back models written to file using `mwrite_yaml()`. Function `yaml_to_cpp()` is also provided to convert the yaml file to mrgsolve cpp file format.

Usage

```
mread_yaml(
  file,
  model = basename(file),
  project = tempdir(),
  update = FALSE,
  ...
)

yaml_to_cpp(file, model = basename(file), project = getwd(), update = TRUE)
```

Arguments

`file`	the yaml file name.
`model`	a new model name to use when calling `mread_yaml()`.
`project`	the directory where the model should be built.
`update`	`TRUE` if model settings should be written into the cpp file in a `$SET` block.
`...`	passed to `mread()`.

Details

Note that `yaml_to_cpp()` by default writes model settings into the cpp file. `mread_yaml()` does not write model settings into the file but rather update the model object directly with data read back from the `yaml` file.

Value

A model object.

See Also

`mwrite_yaml()`

Examples

```
mod <- house()

temp <- tempfile(fileext = ".yaml")

mwrite_yaml(mod, file = temp)

# Note: this model is not compiled
mod <- mread_yaml(temp, model = "new-house", compile = FALSE)
mod

cppfile <- yaml_to_cpp(temp, project = tempdir())

readLines(cppfile)
```

---

mrgsim *Simulate from a model object*

Description

This function sets up the simulation run from data stored in the model object as well as arguments passed in. Use `mrgsim_q()` instead to benchmark mrgsolve or to do repeated quick simulation for tasks like parameter optimization, sensitivity analyses, or optimal design. See mrgsim_variants for other mrgsim-like functions that have more focused inputs. `mrgsim_df` coerces output to data.frame prior to returning.

Usage

```
mrgsim(x, data = NULL, idata = NULL, events = NULL, nid = NULL, ...)

mrgsim_df(..., output = "df")

do_mrgsim(
```

```
  x,
  data,
  idata = no_idata_set(),
  carry_out = carry.out,
  carry.out = character(0),
  recover = character(0),
  seed = as.integer(NA),
  Request = character(0),
  output = NULL,
  capture = NULL,
  obsonly = FALSE,
  obsaug = FALSE,
  tgrid = NULL,
  etasrc = "omega",
  recsort = 1,
  deslist = list(),
  descol = character(0),
  filbak = TRUE,
  tad = FALSE,
  nocb = TRUE,
  skip_init_calc = FALSE,
  ss_n = 500,
  ss_fixed = FALSE,
  interrupt = 256,
  ...
)
```

Arguments

x	the model object.
data	NMTRAN-like data set (see data_set()).
idata	a matrix or data frame of model parameters, one parameter per row (see idata_set()).
events	an event object.
nid	integer number of individuals to simulate; only used if idata and data are missing.
...	passed to update() and do_mrgsim().
output	if NULL (the default) a mrgsims object is returned; otherwise, pass df to return a data.frame or matrix to return a matrix.
carry_out	numeric data items to copy into the output.
carry.out	soon to be deprecated; use carry_out instead.
recover	character column names in either data or idata to join back (recover) to simulated data; may be any class (e.g. numeric, character, factor, etc).
seed	deprecated.
Request	compartments or captured variables to retain in the simulated output; this is different than the request slot in the model object, which refers only to model compartments.

capture	character file name used for debugging (not related to $CAPTURE).
obsonly	if TRUE, dosing records are not included in the output.
obsaug	augment the data set with time grid observations; when TRUE and a full data set is used, the simulated output is augmented with an observation at each time in stime(). When using obsaug, a flag indicating augmented observations can be requested by including a.u.g in carry_out.
tgrid	a tgrid object; or a numeric vector of simulation times or another object with an stime method.
etasrc	source for ETA() values in the model; values can include: "omega", "data", "data.all", "idata", or "idata.all"; see 'Details'.
recsort	record sorting flag. Default value is 1. Possible values are 1,2,3,4: 1 and 2 put doses in a data set after padded observations at the same time; 3 and 4 put those doses before padded observations at the same time. 2 and 4 will put doses scheduled through addl after observations at the same time; 1 and 3 put doses scheduled through addl before observations at the same time. recsort will not change the order of your input data set if both doses and observations are given.
deslist	a list of tgrid objects.
descol	the name of a column for assigning designs.
filbak	carry data items backward when the first data set row has time greater than zero.
tad	when TRUE a column is added to simulated output is added showing the time since the last dose. Only data records with evid == 1 will be considered doses for the purposes of tad calculation. The tad can be properly calculated with a dosing lag time in the model as long as the dosing lag time (specified in $MAIN) is always appropriate for any subsequent doses scheduled through addl. This will always be true if the lag time doesn't change over time. But it might (possibly) not hold if the lag time changes prior to the last dose in the addl sequence. This known limitation shouldn't affect tad calculation in most common dosing lag time implementations.
nocb	if TRUE, use next observation carry backward method; otherwise, use locf.
skip_init_calc	don't use $MAIN to calculate initial conditions.
ss_n	maximum number of iterations for determining steady state for the PK system; a warning will be issued if steady state is not achieved within ss_n iterations when ss_fixed is TRUE.
ss_fixed	if FALSE (the default), then a warning will be issued if the system does not reach steady state within ss_n iterations given the model tolerances rtol and atol; if TRUE, the number of iterations for determining steady state are capped at ss_n and no warning will be issued if steady state has not been reached within ss_n dosing iterations. To silence warnings related to steady state, set ss_fixed to TRUE and set ss_n as the maximum number of iterations to try when advancing the system for steady state determination.
interrupt	integer check user interrupt interval; when interrupt is a positive integer, the simulation will check for the user interrupt signal every interrupt simulation records; pass a negative number to never check for the user interrupt interval.

Details

- Use `mrgsim_df()` to return a data frame rather than `mrgsims` object.
- Both `data` and `idata` will be coerced to numeric matrix
- `carry_out` can be used to insert data columns into the output data set. This is partially dependent on the nature of the data brought into the problem.
- When using `data` and `idata` together, an error is generated if an ID occurs in `data` but not `idata`. Also, when looking up data in `idata`, ID in `idata` is assumed to be uniquely keyed to ID in `data`. No error is generated if ID is duplicated in `data`; parameters will be used from the first occurrence found in `idata`.
- `carry_out`: `idata` is assumed to be individual-level and variables that are carried from `idata` are repeated throughout the individual's simulated data. Variables carried from `data` are carried via last-observation carry forward. `NA` is returned from observations that are inserted into simulated output that occur prior to the first record in `data`.
- `recover`: this is similar to `carry_out` with respect to end result, but it uses a different process. Columns to be recovered are cached prior to running the simulation, and then joined back on to the simulated data. So, whereas `carry_out` will only accept numeric data items, `recover` can handle data frame columns of any type. There is a small decrease in performance with `recover` compared to `carry_out`, but it is likely that the performance difference is difficult to perceive (when the simulation runs very fast) or only a small fractional increase in run time when the simulation is very large. And any performance hit is likely to be well worth it in light of the convenience gain. Just think carefully about using this feature when every millisecond counts.
- `etasrc`: this argument lets you control where `ETA(n)` come from in the model. When `etasrc` is set to `"omega"` (the default), `ETAs` will be simulated from a multivariate normal distribution defined by the `$OMEGA` blocks in the model. Alternatively, input `data` or `idata` sets can be used to pass in fixed `ETA(n)` by setting `etasrc` to `"data"`, `"idata"`, `"data.all"` or `"idata.all"`. When `etasrc` is set to `"data"` or `"data.all"`, the input data set will be scanned for columns called `ETA1`, `ETA2`, ..., `ETAn` and those values will be copied into the appropriate slot in the `ETA()` vector. Only the first record for each individual will be copied into `ETA()`; all records after the first will be ignored. When there are more than `9` `ETAs` in a model, NONMEM will start naming the outputs `ET10`, `ET11` etc rather than `ETA10` and `ETA11`. When mrgsolve is looking for these columns, it will first search, for example, `ET10` and use that value if it is found. If `ET10` isn't found and there are more than `9` `ETAs`, then it will *also* search for `ETA10`. An error will be generated in case mrgsolve finds both the `ETA` and `ET` name variant for the tenth and higher `ETA` (e.g. it is an error to have both `ETA10` and `ET10` in the data set). When mrgsolve is searching for `ETA` columns in the data set, it will *only* look for `ETAn` up to the number of rows (or columns) in all the model `$OMEGA` blocks. For example, if `$OMEGA` is 5x5, only `ETA1` through `ETA5` will be searched. An error will be generated in case mrgsolve finds *no* columns with `ETAn` names and something other than `etasrc = "omega"` was passed. When `etasrc = "data"` and an `ETAn` column is missing from the data set, the missing `ETA()` will be set to `0`. Alternatively, the user can pass `etasrc = "data.all"` which causes an error to be generated if any `ETAn` is missing from the data set. Use this option when you intend to have *all* `ETAs` attached to the data set and want an error generated if mrgsolve finds one or more of them is missing. Using `etasrc ="idata"` or `"idata.all"`, the behavior is identical to `"data"` (or `"data.all"`), except mrgsolve will look at the idata set rather than data set.

Value

An object of class mrgsims.

See Also

mrgsim_variants, mrgsim_q()

Examples

```
## example("mrgsim")

e <- ev(amt = 1000)

mod <- mrgsolve::house()

out <- mod %>% ev(e) %>% mrgsim()

plot(out)

out <- mod %>% ev(e) %>% mrgsim(end=22)

out

data(exTheoph)

out <- mod %>% data_set(exTheoph) %>% mrgsim()

out

out <- mod %>% mrgsim(data=exTheoph)

out <- mrgsim(mod, data=exTheoph, obsonly=TRUE)

out

out <- mod %>% mrgsim(data=exTheoph, obsaug=TRUE, carry_out="a.u.g")

out

out <- mod %>% ev(e) %>% mrgsim(outvars="CP,RESP")

out

a <- ev(amt = 1000, group = 'a')
b <- ev(amt = 750, group = 'b')
data <- as_data_set(a,b)

out <- mrgsim_d(mod, data, recover="group")

out
```

mrgsim_q *Simulate from a model object with quicker turnaround*

Description

Use the function when you would usually use mrgsim_d(), but you need a quicker turnaround time. The timing differences might be difficult to detect for a single simulation run but could become appreciable with repeated simulation. See **Details** for important differences in how mrgsim_q() is invoked compared to mrgsim() and mrgsim_d(). This function should always be used for benchmarking simulation time with mrgsolve.

Usage

```
mrgsim_q(
  x,
  data,
  recsort = 1,
  stime = numeric(0),
  output = "mrgsims",
  skip_init_calc = FALSE,
  simcall = 0,
  etasrc = "omega"
)
```

Arguments

x	a model object.
data	a simulation data set.
recsort	record sorting flag.
stime	a numeric vector of observation times; these observation times will only be added to the output if there are no observation records in data.
output	output data type; if "mrgsims", then the default output object is returned; if "df"‘ then a data frame is returned.
skip_init_calc	don't use $MAIN to calculate initial conditions.
simcall	not used; only the default value of 0 is allowed.
etasrc	source for ETA() values in the model; values can include: "omega", "data", "data.all", "idata", or "idata.all"; see 'Details' in mrgsim().

Details

mrgsim_q() mainly cuts some of the overhead from the simulation. So, the primary efficiency gain from using mrgsim_q() comes when the simulation executes very quickly. It is unlikely you will see a big performance difference between mrgsim_q() and mrgsim() when the model is difficult to solve or if there is a large input data set.

This function does not support the piped simulation workflow. All arguments must be passed into the function except for x.

A data set is required for this simulation workflow. The data set can have only dosing records or doses with observations. When the data set only includes doses, a single numeric vector of observation times should be passed in.

This simulation workflow does not support Req (request) functionality. All compartments and captured variables will always be returned in the simulation output.

This simulation workflow does not support carry-out functionality.

This simulation workflow does not accept arguments to be passed to update(). This must be done by a separate call to update().

This simulation workflow does not support use of event objects. If an event object is needed, it should be converted to a data set prior to the simulation run (see as_data_set() or as.data.frame()).

This simulation workflow does not support idata sets or any feature enabled by idata set use. Individual level parameters should be joined onto the data set prior to simulation. Otherwise mrgsim_i() or mrgsim_ei() should be used.

By default, a mrgsims object is returned (as with mrgsim()). Use the output = "df" argument to request a plain data.frame of simulated data on return.

Value

By default, an object of class mrgsims. Use output = "df" to return a data frame.

See Also

mrgsim(), mrgsim_variants, qsim()

Examples

```
mod <- mrgsolve::house()

data <- expand.ev(amt = c(100, 300, 1000))

out <- mrgsim_q(mod, data)

out
```

---

mrgsim_variants *mrgsim variant functions*

Description

These functions are called by mrgsim() and have explicit input requirements written into the function name. The motivation behind these variants is to give the user a clear workflow with specific, required inputs as indicated by the function name. Use mrgsim_q() instead to benchmark mrgsolve or to do repeated quick simulation for tasks like parameter optimization, sensitivity analyses, or optimal design.

Usage

```
mrgsim_e(x, events, idata = NULL, data = NULL, ...)

mrgsim_d(x, data, idata = NULL, events = NULL, ...)

mrgsim_ei(x, events, idata, data = NULL, ...)

mrgsim_di(x, data, idata, events = NULL, ...)

mrgsim_i(x, idata, data = NULL, events = NULL, ...)

mrgsim_0(x, idata = NULL, data = NULL, events = NULL, ...)
```

Arguments

x	the model object.
events	an event object.
idata	a matrix or data frame of model parameters, one parameter per row (see idata_set()).
data	NMTRAN-like data set (see data_set()).
...	passed to update() and do_mrgsim().

Details

Important: all of these functions require that data, idata, and/or events be pass directly to the functions. They will not recognize these inputs from a pipeline.

- mrgsim_e simulate using an event object
- mrgsim_ei simulate using an event object and idata_set
- mrgsim_d simulate using a data_set
- mrgsim_di simulate using a data_set and idata_set
- mrgsim_i simulate using a idata_set
- mrgsim_0 simulate using just the model
- mrgsim_q simulate from a data set with quicker turnaround (see mrgsim_q())

See Also

mrgsim(), mrgsim_q(), qsim()

mrgsims_dplyr *Methods for handling output with dplyr verbs*

Description

These methods modify the data in a mrgsims object and return a data frame. Contrast with the functions in mrgsims_modify.

Usage

```
## S3 method for class 'mrgsims'
pull(.data, ...)

## S3 method for class 'mrgsims'
filter(.data, ...)

## S3 method for class 'mrgsims'
group_by(.data, ..., .add = FALSE)

## S3 method for class 'mrgsims'
distinct(.data, ..., .keep_all = FALSE)

## S3 method for class 'mrgsims'
mutate(.data, ...)

## S3 method for class 'each'
summarise(...)

## S3 method for class 'mrgsims'
summarise(.data, ...)

## S3 method for class 'mrgsims'
do(.data, ..., .dots)

## S3 method for class 'mrgsims'
select(.data, ...)

## S3 method for class 'mrgsims'
slice(.data, ...)

as_data_frame.mrgsims(x, ...)

## S3 method for class 'mrgsims'
as_tibble(x, ...)

as.tbl.mrgsims(x, ...)
```

Arguments

.data	an mrgsims object; passed to various dplyr functions.
...	passed to other methods.
.add	passed to dplyr::group_by().
.keep_all	passed to dplyr::distinct().
.dots	passed to various dplyr functions.
x	mrgsims object.

Details

For the select_sims function, the dots ... must be either compartment names or variables in $CAPTURE. An error will be generated if no valid names are selected or the names for selection are not found in the simulated output.

See Also

mrgsims_modify

Examples

```
out <- mrgsim(house(), events = ev(amt = 100), end = 5, delta=1)

dplyr::filter(out, time==2)

dplyr::mutate(out, label = "abc")

dplyr::select(out, time, RESP, CP)
```

---

mrgsims_modify *Methods for modifying mrgsims objects*

Description

These functions modify the simulated data in an mrgsims object and return the modified object. Contrast with the functions in mrgsims_dplyr.

Usage

```
mutate_sims(.data, ...)

select_sims(.data, ...)

filter_sims(.data, ...)
```

Arguments

.data	a mrgsims object.
...	other arguments passed to the dplyr functions.

See Also

mrgsims_dplyr

Examples

```
out <- mrgsim(house(), events = ev(amt = 100))

filter_sims(out, time > 2)

mutate_sims(out, label = "abc")

select_sims(out, RESP, CP)
```

---

mutate.ev *dplyr verbs for event objects*

Description

dplyr verbs for event objects

Usage

```
## S3 method for class 'ev'
mutate(.data, ...)

## S3 method for class 'ev'
select(.data, ...)

## S3 method for class 'ev'
filter(.data, ...)
```

Arguments

.data	the event object.
...	passed to the dplyr function.

mwrite_cpp *Write a model to native mrgsolve format*

Description

Model code is written to a file in native mrgsolve format. This can be useful for (1) breaking connection to NONMEM modeling outputs that are imported by `$NMXML` or `$NMEXT` and (2) saving model updates (e.g., an updated parameter list). Models can be read back using `mread()`.

Usage

```
mwrite_cpp(x, file, update = TRUE)
```

Arguments

`x`	a model object.
`file`	output file name; if non-character (e.g., `NULL`), no output will be written to file.
`update`	`TRUE` if model settings should be written into the cpp file in a `$SET` block.

Details

See important details in `mwrite_yaml()`.

Value

A list containing data that was written out to the cpp file, with added item `file`, is returned invisibly.

See Also

`mwrite_yaml()`, `yaml_to_cpp()`

Examples

```
temp <- tempfile(fileext = ".mod")

mod <- modlib("pk1", compile = FALSE)

x <- mwrite_cpp(mod, file = temp)

mod <- mread(x$file, compile = FALSE)

mod
```

`mwrite_yaml` *Write model code to yaml format*

Description

Model code is written to a readable, transport format. This transport format can be useful for (1) breaking connection to NONMEM modeling outputs that are imported by `$NMXML` or `$NMEXT` and (2) saving model updates (e.g., an updated parameter list). Models can be read back using `mread_yaml()` or converted to mrgsolve cpp format with `yaml_to_cpp()`.

Usage

```
mwrite_yaml(x, file, digits = 8)
```

Arguments

`x`	a model object.
`file`	output file name; if non-character (e.g., `NULL`), no output will be written to file.
`digits`	precision to use when writing outputs.

Details

Parameters and omega and sigma matrices that were imported via `$NMXML` or `$NMEXT` will be written into the yaml file and the NONMEM import blocks will be dropped. This allows the user to load a model based on a NONMEM run without having a connection to that output (e.g., `root.xml` or `root.ext`). Given that the connection to the NONMEM modeling outputs is broken when writing to yaml, any update to the NONMEM run will only be propagated to the yaml file when `mwrite_yaml()` is run again.

The yaml file does not currently have the ability to track other external dependencies, such as user-defined header files or other code that might be sourced in by the user when the model is loaded via `mread()`. NONMEM xml and ext files imported by `$NMXML` or `$NMEXT` are the *only* external dependencies that are accounted for in the yaml transport file.

Value

A list containing data that was written out to the yaml file, with added item `file`, is returned invisibly.

See Also

`mread_yaml()`, `yaml_to_cpp()`

Examples

```
mod <- house()

temp1 <- tempfile(fileext = ".yaml")

x <- mwrite_yaml(mod, temp1)

readLines(temp1)
```

`names,mrgmod-method` *Get all names from a model object*

Description

Get all names from a model object

Usage

```
## S4 method for signature 'mrgmod'
names(x)
```

Arguments

`x`	the model object

Examples

```
mod <- mrgsolve::house()
names(mod)
```

`nmext` *Import model estimates from a NONMEM ext file*

Description

Import model estimates from a NONMEM ext file

Usage

```
nmext(
  run = NA_real_,
  project = getwd(),
  file = paste0(run, ".ext"),
  path = NULL,
  root = c("cppfile", "working"),
  index = "last",
  theta = TRUE,
  omega = TRUE,
  sigma = TRUE,
  olabels = NULL,
  slabels = NULL,
  oprefix = "",
  sprefix = "",
  tname = "THETA",
  oname = "...",
  sname = "...",
  read_fun = "data.table",
  env = NULL
)
```

Arguments

run	run number.
project	project directory.
file	deprecated; use path instead.
path	full path to NONMEM ext file.
root	the directory that path and project are relative to; this is currently limited to the working directory or cppdir, the directory where the model file is located.
index	the estimation number to return; "last" will return the last estimation results; otherwise, pass an integer indicating which estimation results to return.
theta	logical; if TRUE, the $THETA vector is returned.
omega	logical; if TRUE, the $OMEGA matrix is returned.
sigma	logical; if TRUE, the $SIGMA matrix is returned.
olabels	labels for $OMEGA.
slabels	labels for $SIGMA.
oprefix	prefix for $OMEGA labels.
sprefix	prefix for $SIGMA labels.
tname	name for $THETA.
oname	name for $OMEGA.
sname	name for $SIGMA.
read_fun	function to use when reading the ext file.
env	internal use only.

See Also

nmxml(), read_nmext()

---

nmxml *Import model estimates from a NONMEM xml file*

Description

Import model estimates from a NONMEM xml file

Usage

```
nmxml(
  run = numeric(0),
  project = character(0),
  file = character(0),
  path = character(0),
  root = c("cppfile", "working"),
  theta = TRUE,
  omega = TRUE,
  sigma = TRUE,
  olabels = NULL,
  slabels = NULL,
  oprefix = "",
  sprefix = "",
  tname = "THETA",
  oname = "...",
  sname = "...",
  index = "last",
  xpath = ".//nm:estimation",
  env = NULL
)
```

Arguments

run	run number.
project	project directory.
file	deprecated; use path instead.
path	the complete path to the run.xml file.
root	the directory that path and project are relative to; this is currently limited to the working directory or cppdir, the directory where the model file is located.
theta	logical; if TRUE, the $THETA vector is returned.
omega	logical; if TRUE, the $OMEGA matrix is returned.
sigma	logical; if TRUE, the $SIGMA matrix is returned.

olabels	labels for $OMEGA.
slabels	labels for $SIGMA.
oprefix	prefix for $OMEGA labels.
sprefix	prefix for $SIGMA labels.
tname	name for $THETA.
oname	name for $OMEGA.
sname	name for $SIGMA.
index	the estimation number to return; "last" will return the last estimation results; otherwise, pass an integer indicating which estimation results to return.
xpath	xml path containing run results; if the default doesn't work, consider using .//estimation as an alternative; see details.
env	internal use only.

Details

If run and project are supplied, the .xml file is assumed to be located in run.xml, in directory run off the project directory. If file is supplied, run and project arguments are ignored.

This function requires that the xml2 package be installed and loadable. If requireNamespace("xml2") fails, an error will be generated.

nmxml usually expects to find run results in the xpath called .//nm:estimation. Occasionally, the run results are not stored in this namespace but no namespaces are found in the xml file. In this case, the user can specify the xpath containing run results. Consider trying .//estimation as an alternative if the default fails.

Value

A list with theta, omega and sigma elements, depending on what was requested.

See Also

nmext

Examples

```
if(requireNamespace("xml2")) {
  proj <- system.file("nonmem", package = "mrgsolve")
  mrgsolve:::nmxml(run = 1005, project = proj)
}
```

numerics_only *Prepare data.frame for input to mrgsim()*

Description

Prepare data.frame for input to mrgsim()

Usage

```
numerics_only(x, quiet = FALSE, convert_lgl = FALSE)
```

Arguments

x	a input data set.
quiet	logical indicating whether or not warnings should be printed.
convert_lgl	if TRUE, convert logical columns with as.integer().

obsaug *Augment observations in the simulated output*

Description

Augment observations in the simulated output

Usage

```
obsaug(x, value = TRUE, ...)
```

Arguments

x	model object
value	the value for obsaug
...	passed along There is also a obsaug argument to mrgsim that can be set to accomplish the same thing as a call to obsaug in the pipeline.

obsonly *Collect only observation records in the simulated output*

Description

Collect only observation records in the simulated output

Usage

```
obsonly(x, value = TRUE, ...)
```

Arguments

x	model object.
value	use ‘TRUE‘ to collect and return observation records only.
...	not used.

Details

There is also an ‘obsonly‘ argument to [mrgsim()] that can be set to accomplish the same thing as a call to ‘obsonly()‘ in the pipeline.

omega *Manipulate OMEGA matrices*

Description

The primary function is `omat()` that can be used to both get the `$OMEGA` matrices out of a model object and to update `$OMEGA` matrices in a model object.

Usage

```
omat(.x, ...)

## S4 method for signature 'missing'
omat(.x, ...)

## S4 method for signature 'matrix'
omat(.x, ..., labels = list())

## S4 method for signature 'NULL'
omat(.x, ...)

## S4 method for signature 'list'
omat(.x, ...)
```

```
## S4 method for signature 'omegalist'
omat(.x, ...)

## S4 method for signature 'mrgmod'
omat(.x, ..., make = FALSE, open = FALSE)

## S4 method for signature 'mrgsims'
omat(.x, make = FALSE, ...)
```

Arguments

.x	a matrix, list of matrices or matlist object.
...	passed to other functions, including modMATRIX().
labels	character vector of names for $OMEGA elements; must be equal to number of rows/columns in the matrix.
make	logical; if TRUE, matrix list is rendered into a single matrix.
open	passed to merge.list().
x	matlist object.

See Also

smat(), dmat(), bmat(), cmat()

Examples

```
# example("omega")
mat1 <- matrix(1)
mat2 <- diag(c(1,2,3))
mat3 <- matrix(c(0.1, 0.002, 0.002, 0.5), 2,2)
mat4 <- dmat(0.1, 0.2, 0.3, 0.4)

omat(mat1)
omat(mat1, mat2, mat3)
omat(A = mat1, B = mat2, C = mat3)

mod <- mrgsolve::house() %>% omat(mat4)

omat(mod)
omat(mod, make = TRUE)
as.matrix(omat(mod))
```

outvars *Show names of current output variables*

Description

Outputs can include model compartments or variables defined in the model that have been marked to capture in simulated output.

Usage

```
outvars(x, unlist = FALSE)
```

Arguments

x	model object.
unlist	if TRUE then a character vector (rather than list) is returned.

Value

When unlist is FALSE (default) : a named list, with cmt showing names of output compartments and capture giving names of output variables in capture. When unlist is TRUE, then a single, unnamed character vector of outvar names is returned.

Examples

```
mod <- mrgsolve::house()
outvars(mod)
```

param *Create and work with parameter objects*

Description

See numericlist for methods to deal with parameter_list objects.

Usage

```
param(.x, ...)

## S4 method for signature 'mrgmod'
param(.x, .y = NULL, ..., .pat = "*", .strict = FALSE)

## S4 method for signature 'mrgsims'
param(.x, ...)
```

```
## S4 method for signature 'missing'
param(..., .strict = TRUE)

## S4 method for signature 'list'
param(.x, ...)

## S4 method for signature 'ANY'
param(.x, ...)

allparam(.x)
```

Arguments

.x	the model object.
...	passed along or name/value pairs to update the parameters in a model object; when passing new values this way, all values must be numeric and all all names must exist in the parameter list for .x.
.y	an object to be merged into parameter list; non-NULL values must be named list, data.frame, numeric vector, or parameter_list object; named items that do not exist in the parameter list are allowed and will be silently ignored; use the .strict argument to require that all names in .y exist already in the parameter list.
.pat	a regular expression (character) to be applied as a filter for which parameters to show when printing.
.strict	if TRUE, all names to be updated must be found in the parameter list.

Details

Can be used to either get a parameter list object from a mrgmod model object or to update the parameters in a model object. For both uses, the return value is a parameter_list object. For the former use, param() is usually called to print the parameters to the screen, but the parameter_list object can also be coerced to a list or numeric R object.

Use allparam() to get a parameter_list object including both model parameters and data items listed in $FIXED.

The update to parameters can be permissive (candidates with names that don't exist in the parameter list are silently ignored) or strict (all candidates must already exist in the parameter list). When passing candidate values via ..., the update is strict and an error is generated if you pass a name that isn't found in the parameter list. When candidate values are passed as a named object via .y, then the update is permissive. Any permissive update can be made strict (error if foreign names are found in the candidates) by passing .strict = TRUE.

An alternative is to assess the incoming names using inventory().

Value

An object of class parameter_list (see numericlist).

See Also

inventory()

Examples

```
## example("param")

mod <- house()

param(mod)

param(mod, .pat="^(C|F)") ## may be useful when large number of parameters

class(param(mod))

param(mod)$KA

param(mod)[["KA"]]

as.list(param(mod))

as.data.frame(param(mod))

mod <- param(mod, CL = 1.2)

new_values <- list(CL = 1.3, VC = 20.5)

mod <- param(mod, new_values)
```

---

param_tags *Return parameter tags*

Description

Use this function if you added the `@covariates` or `@input` attributes or specified a user-defined tag (via `@tag`) in one or more parameter blocks and need to extract that information. Also, using the `$INPUT` block to declare parameters will automatically add the `input` tag (via `@input`). Once these attributes / tags are added, you can use check_data_names() to reconcile names of input data sets against tagged model parameters.

Usage

```
param_tags(x)
```

Arguments

x	mrgsolve model object.

Value

A data frame listing parameter names and their tags.

Model specification

Note: it is good practice to tag parameters where appropriate with `input` or `covariates` as these will automatically be expected on input data when you call `check_data_names()`. User-defined tags are also possible, but you will need to alert `check_data_names()` to look for them.

Model Specification Examples

You can use the `$INPUT` block to add the `input` tag on these parameters

```
$INPUT
STUDY = 101, WT = 70, DVID = 1
```

Tag some covariates in the model

```
$PARAM @covariates
WT = 70, SEX = 1, EGFR = 110
```

A user-defined tag

```
$PARAM @tag flags
FFLAG = 1, DFLAG = 0
```

See Also

`check_data_names()`

Examples

```
mod <- mrgsolve::house()

param_tags(mod)
```

PKMODEL *Parse PKMODEL BLOCK data*

Description

Parse PKMODEL BLOCK data

Usage

```
PKMODEL(
  ncmt = 1,
  depot = FALSE,
  cmt = NULL,
  advan = NULL,
  trans = NULL,
  env = list(),
  pos = 1,
  ...
)
```

Arguments

ncmt	number of compartments; must be 1 (one-compartment, not including a depot dosing compartment), 2 (two-compartment model, not including a depot dosing compartment), or 3 (three-compartment model, not including a depot dosing compartment).
depot	logical indicating whether to add depot compartment.
cmt	compartment names as comma-delimited character.
advan	ADVAN subroutine number; can be 1, 2, 3, 4, 11, or 12; when specified, ncmt and depot are derived from the ADVAN number and the appropriate compartments are registered to the model unless specified elsewhere (see **Details**).
trans	the parameterization for the PK model; must be 1, 2, 4, or 11.
env	parse environment.
pos	block position number.
...	not used.

Details

When using $PKMODEL, certain symbols must be defined in the model specification depending on the value of ncmt, depot and trans.

- ncmt 1, depot FALSE, trans 2: CL, V
- ncmt 1, depot TRUE , trans 2: CL, V, KA
- ncmt 2, depot FALSE, trans 4: CL, V1, Q, V2
- ncmt 2, depot TRUE , trans 4: CL, V2, Q, V3, KA
- ncmt 3, depot FALSE, trans 4: CL, V1, Q2, V2, Q3, V3
- ncmt 3, depot TRUE , trans 4: CL, V2, Q3, V3, KA, Q4, V4

If trans=11 is specified, use the symbols listed above for the ncmt / depot combination, but append i at the end (e.g. CLi or Q2i or KAi).

If trans=1, the user must utilize the following symbols:

- pred_CL for clearance

- pred_V or pred_V2 for central compartment volume of distribution
- pred_Q for intercompartmental clearance
- pred_V3 for peripheral compartment volume of distribution
- pred_KA for absorption rate constant
- pred_Q2 for second intercompartmental clearance (3-cmt)
- pred_VP2 or pred_V4 for second peripheral compartment volume of distribution (3-cmt)

When advan is supplied by the user, default compartments are registered in the model unless specified elsewhere. Compartment names are A1, A2, etc. to the number of compartments for the specified advan. These compartments will *not* be added in case (1) the model contains a $CMT block (2) the model contains a $INIT block or (3) no compartments have been registered in the model at the time $PKMODEL is processed (for example, via $YAML).

See Also

BLOCK_PARSE

Examples

```
## Not run:
code <- '
$PARAM CL = 1, V2 = 20, Q = 2, V3 = 10, KA = 1
$PKMODEL ncmt = 2, depot = TRUE, cmt = "GUT CENT PERIPH"
'
mod <- mcode("pk2-example", code)

code <- '
$PARAM CL = 1, V2 = 20, Q3 = 2, V3 = 10, Q4 = 0.5, V4 = 50, KA = 1
$PKMODEL advan = 12
'
mod <- mcode("advan12-example", code)

## End(Not run)
```

---

plot_mrgsims *Generate a quick plot of simulated data*

Description

Generate a quick plot of simulated data

Usage

```
## S4 method for signature 'mrgsims,missing'
plot(x, limit = 16, ...)

## S4 method for signature 'mrgsims,formula'
plot(
  x,
  y,
  limit = 16,
  show.grid = TRUE,
  outer = TRUE,
  type = "l",
  lwd = 2,
  ylab = "value",
  groups = ID,
  scales = list(y = list(relation = "free")),
  fixy = NULL,
  logy = NULL,
  logbr = 0,
  equispaced.log = FALSE,
  ...
)

## S4 method for signature 'mrgsims,character'
plot(x, y, ...)
```

Arguments

x	mrgsims object.
limit	limit the the number of panels to create.
...	other arguments passed to lattice::xyplot().
y	formula used for plotting.
show.grid	logical indicating whether or not to draw panel.grid.
outer	passed to lattice::xyplot().
type	passed to lattice::xyplot().
lwd	passed to lattice::xyplot().
ylab	passed to lattice::xyplot().
groups	passed to lattice::xyplot().
scales	passed to lattice::xyplot().
fixy	make the y-axis scale the same for all variables; ignored if scales is not a list.
logy	plot the y variables on log scale; ignored if scales is not a list.
logbr	log scale breaks indicator; use 1 for breaks every log unit; use 3 for breaks every half log unit; use 0 for default breaks; ignored if scales is not a list.
equispaced.log	see scales argument in lattice::xyplot(); ignored if scales is not a list.

Examples

```
mod <- mrgsolve::house(end=48, delta=0.2) %>% init(GUT=1000)

out <- mrgsim(mod)

plot(out)

plot(out, subset=time <= 24)

plot(out, GUT + CP ~ .)

plot(out, CP + RESP ~ time, col = "black", fixy = TRUE, lty = 2)

## Not run:
plot(out, "CP RESP, GUT")

## End(Not run)
```

`plot_sims` *Plot data as an mrgsims object*

Description

Plot data as an mrgsims object

Usage

```
plot_sims(.data, ..., .f = NULL, .dots = list())
```

Arguments

`.data`	a data frame
`...`	unquoted column names to plot on y-axis
`.f`	a formula to plot
`.dots`	extra arguments passed to `lattice::xyplot`

Details

This function is only intended for use with data frames that were created by modifying an `mrgsims` object.

Examples

```
mod <- mrgsolve::house() %>% ev(amt = 100)

out <- mrgsim(mod)
out_df <- dplyr::mutate(out, time <= 72)

plot(out)
plot_sims(out, CP, RESP)

## Not run:
plot_sims(out, .f = ~ CP + RESP)
plot_sims(out, .f = CP + RESP ~ time)

## End(Not run)
```

---

qsim *Basic, simple simulation from model object*

Description

This is just a lighter version of `mrgsim()`, with fewer options but with better efficiency in certain cases. See **Details**.

Usage

```
qsim(
  x,
  data,
  idata = no_idata_set(),
  obsonly = FALSE,
  tgrid = NULL,
  recsort = 1,
  tad = FALSE,
  Req = NULL,
  outvars = Req,
  skip_init_calc = FALSE,
  output = "mrgsims"
)
```

Arguments

x	the model object.
data	can be either event object or data set.
idata	a matrix or data frame of model parameters, one parameter per row (see `idata_set()`).
obsonly	if TRUE, dosing records are not included in the output.

tgrid	a tgrid object; or a numeric vector of simulation times or another object with an stime method.
recsort	record sorting flag. Default value is 1. Possible values are 1,2,3,4: 1 and 2 put doses in a data set after padded observations at the same time; 3 and 4 put those doses before padded observations at the same time. 2 and 4 will put doses scheduled through addl after observations at the same time; 1 and 3 put doses scheduled through addl before observations at the same time. recsort will not change the order of your input data set if both doses and observations are given.
tad	when TRUE a column is added to simulated output is added showing the time since the last dose. Only data records with evid == 1 will be considered doses for the purposes of tad calculation. The tad can be properly calculated with a dosing lag time in the model as long as the dosing lag time (specified in $MAIN) is always appropriate for any subsequent doses scheduled through addl. This will always be true if the lag time doesn't change over time. But it might (possibly) not hold if the lag time changes prior to the last dose in the addl sequence. This known limitation shouldn't affect tad calculation in most common dosing lag time implementations.
Req	synonym for outvars.
outvars	output items to request; if missing, then only captured items will be returned in the output.
skip_init_calc	don't use $MAIN to calculate initial conditions.
output	output data type; the default is mrgsims, which returns the default output object; other options include df (for data.frame) or matrix.

Details

qsim() mainly cuts some of the overhead from the simulation. So, the primary efficiency gain from using qsim() comes when the simulation executes very quickly. It is unlikely you will see a big performance difference between qsim() and mrgsim() when the model is difficult to solve or if there is a large input data set.

There is no pipeline interface for this function; all configuration options (see **Arguments**) must be passed as formal arguments to the function. You can't carry_out, Request specific columns, or pass items in for update. Some other limitations, but only convenience-related. See **Arguments** for available options. Specifically, there is no ... argument for this function. Use the update() method to update the model object.

See Also

mrgsim_q(), mrgsim(), mrgsim_variants

Examples

```
mod <- mrgsolve::house()

dose <- ev(amt = 100)

out <- qsim(mod,dose)
```

read_nmext *Extract estimates from NONMEM ext file*

Description

This function retrieves NONMEM estimates for use in the mrgsolve model when `$NMEXT` is invoked. See `nmext()`.

Usage

```
read_nmext(
  run = NA_real_,
  project = getwd(),
  file = paste0(run, ".ext"),
  path = NULL,
  read_fun = c("data.table", "read.table"),
  index = "last"
)
```

Arguments

`run`	a run number or run identifier.
`project`	the NONMEM project directory.
`file`	the `ext` file name.
`path`	full path and file name for `ext` file.
`read_fun`	function to read the `ext` file; `data.table::fread()` will be used if available; otherwise `utils::read.table()` is used.
`index`	selects the table number whose results will be returned; use value "last" to select the last table in the `.ext` file; or pass an integer specifying the table number; in case there is exactly one table in the `.ext` file, pass the value "single" to bypass parsing the file to look for sub tables (this might be useful when BAYES analysis was performed as the only estimation method and there are 10000s of posterior samples in the file).

Value

A list with param, omega, and sigma in a format ready to be used to update a model object.

Examples

```
project <- system.file("nonmem", package = "mrgsolve")

est <- read_nmext(1005, project = project)

est$param
```

```
est$omega

est$sigma

est <- read_nmext(2005, project = project, index = 3)
```

`realize_addl` *Make addl doses explicit in an event object or data set*

Description

When doses are scheduled with `ii` and `addl`, the object is expanded to include one record for every dose. In the result, no record with have `ii` or `addl` set to non-zero value.

Usage

```
realize_addl(x, ...)

## S3 method for class 'data.frame'
realize_addl(
  x,
  warn = FALSE,
  mark_new = FALSE,
  fill = c("inherit", "na", "locf"),
  ...
)

## S3 method for class 'ev'
realize_addl(x, ...)
```

Arguments

`x`	a `data_set` data frame or an event object (see **Details**).
`...`	not used.
`warn`	if `TRUE` a warning is issued if no `ADDL` or `addl` column is found.
`mark_new`	if `TRUE`, a flag is added to indicate new columns.
`fill`	specifies how to handle non-dose related data columns in new data set records; this option is critical when handling data sets with time-varying, non-dose-related data items; see **Details**.

Details

If no `addl` column is found the data frame is returned and a warning is issued if `warn` is true. If `ii`, `time`, or `evid` are missing, an error is generated.

If a grouped data.frame (via `dplyr::group_by()`) is passed, it will be ungrouped.

Use caution when passing in data that has non-dose-related data columns that vary within a subject and pay special attention to the `fill` argument. By definition, `realize_addl()` will add new rows to your data frame and it is not obvious how the non-dose-related data should be handled in these new rows. When `inherit` is chosen, the new records have non-dose-related data that is identical to the originating dose record. This should be fine when these data items are not varying with time, but will present a problem when the data are varying with time. When `locf` is chosen, the missing data are filled in with `NA` and an last observation carry forward operation is applied to **every** column in the data set. This may not be what you want if you already had missing values in the input data set and want to preserve that missingness. When `na` is chosen, the missing data are filled in with `NA` and no `locf` operation is applied. But note that these missing values may be problematic for a mrgsolve simulation run. If you have any time-varying columns or missing data in your data set, be sure to check that the output from this function is what you were expecting.

Value

A data.frame or event object, consistent with the type of `x`. The `ii` and `addl` columns will all be set to zero. The result is always ungrouped.

Examples

```
e <- ev(amt = 100, ii = 12, addl = 3)

realize_addl(e)

a <- ev(amt = 100, ii = 12, addl = 2, WT = 69)
b <- ev(amt = 200, ii = 24, addl = 2, WT = 70)
c <- ev(amt =  50, ii =  6, addl = 2, WT = 71)

e <- ev_seq(a,b,c)
realize_addl(e, mark_new = TRUE)
```

Req *Request simulated output*

Description

Use this function to select, by name, either compartments or derived variables that have been captured (see CAPTURE) into the simulated output.

Usage

```
Req(x, ...)

req(x, ...)

## S3 method for class 'mrgmod'
req(x, ...)
```

Arguments

x	model object.
...	unquoted names of compartments or tabled items.

Details

There is also a Req argument to mrgsim() that can be set to accomplish the same thing as a call to Req in the pipeline.

Note the difference between req and Req: the former only selects compartments to appear in output while the latter selects both compartments and captured items. Also, when there are items explicitly listed in Req, all other compartments or captured items not listed there are ignored. But when compartments are selected with req all of the captured items are returned. Remember that req is strictly for compartments.

Examples

```
mod <- mrgsolve::house()

mod %>% Req(CP,RESP) %>% ev(amt=1000) %>%  mrgsim()
```

---

reserved *Reserved words*

Description

Reserved words

Usage

```
reserved()
```

Details

Note: this function is not exported; you must go into the mrgsolve namespace by using the mrgsolve::: prefix.

Examples

```
mrgsolve:::reserved()
```

`reset_tol` *Reset all model tolerances*

Description

These functions reset both scalar and customized values for both relative and absolute tolerances. All functions reset tolerances to a single, common `rtol` or `atol`. The functions do *not* change which tolerance configuration is used for simulation (e.g., scalar or customized); see `use_custom_tol()` and `use_scalar_tol()` to make that change in the model object.

Usage

```
reset_tol(x, rtol = NULL, atol = NULL)

reset_rtol(x, rtol = NULL)

reset_atol(x, atol = NULL)
```

Arguments

`x`	a model object.
`rtol`	global relative tolerance for both scalar and customized configurations; if not supplied, the current model's scalar `rtol` value is used.
`atol`	global absolute tolerance for both scalar and customized configurations; if not supplied, the current model's scalar `atol` value is used.

Value

An updated model object.

See Also

`custom_tol()`, `use_custom_tol()`, `use_scalar_tol()`, `get_tol()`

Examples

```
mod <- house()
mod <- reset_tol(mod, rtol = 1e-6, atol = 1e-10)
mod
```

revar *Get model random effect variances and covariances*

Description

Use this function to extract both OMEGA and SIGMA matrices from a model object. Typical use is for display on the R console.

Usage

```
revar(x, ...)

## S4 method for signature 'mrgmod'
revar(x, ...)
```

Arguments

x	model object.
...	passed along.

Value

A named list containing omega and sigma matrices.

Examples

```
mod <- mrgsolve::house()
revar(mod)
```

see *Print model code to the console*

Description

This is a simple way to display the model code on the R console using the model object. The raw argument will return the model code as a character vector.

Usage

```
see(x, ...)

## S4 method for signature 'mrgmod'
see(x, raw = FALSE, ...)
```

Arguments

x	model object.
...	not used.
raw	return the raw code.

Value

NULL is returned invisibly when raw is FALSE; when raw is set to TRUE, the model code is returned as a character vector.

---

sigma *Manipulate SIGMA matrices*

Description

The primary function is smat() which can be used to both get the $SIGMA matrices out of a model object and to update $SIGMA matrices in a model object.

Usage

```
smat(.x, ...)

## S4 method for signature 'missing'
smat(.x, ...)

## S4 method for signature 'matrix'
smat(.x, ..., labels = list())

## S4 method for signature 'list'
smat(.x, ...)

## S4 method for signature 'sigmalist'
smat(.x, ...)

## S4 method for signature 'mrgmod'
smat(.x, ..., make = FALSE, open = FALSE)

## S4 method for signature 'NULL'
smat(.x, ...)

## S4 method for signature 'mrgsims'
smat(.x, make = FALSE, ...)
```

Arguments

.x	a matrix, list of matrices or matlist object.
...	passed to other functions, including modMATRIX().
labels	character vector of names for $SIGMA elements; must be equal to number of rows/columns in the matrix.
make	logical; if TRUE, matrix list is rendered into a single matrix.
open	passed to merge.list().
x	matlist object.

See Also

dmat(), bmat(), cmat()

Examples

```
## example("sigma")
mat1 <- matrix(1)
mat2 <- diag(c(1,2))
mat3 <- matrix(c(0.1, 0.002, 0.002, 0.5), 2,2)
mat4 <- dmat(0.1, 0.2, 0.3, 0.4)

smat(mat1)
smat(mat1, mat2, mat3)
smat(A=mat1, B=mat2, C=mat3)

mod <- mrgsolve::house() %>% smat(mat1)

smat(mod)
smat(mod, make=TRUE)
```

---

simargs *Access or clear arguments for calls to mrgsim()*

Description

As a model object navigates a pipeline prior to simulation, arguments are collected to eventually be passed to mrgsim(). simargs() lets you intercept and possibly clear those arguments.

Usage

```
simargs(x, which = NULL, clear = FALSE, ...)
```

Arguments

x	model object.
which	character with length 1 naming a single arg to get.
clear	logical indicating whether or not to clear args from the model object.
...	not used.

Value

If clear is TRUE, the argument list is cleared and the model object is returned. Otherwise, the argument list is returned.

Examples

```
mod <- mrgsolve::house()
mod %>% Req(CP, RESP) %>% carry_out(evid, WT, FLAG) %>% simargs()
```

---

soloc *Return the location of the model shared object*

Description

This is also the directory where the model is built, which could be the value of tempdir().

Usage

```
soloc(x, short = FALSE)
```

Arguments

x	model object.
short	logical; if TRUE, solocs will be rendered with a short path name.

Value

A string containing the full path to the model shared object.

Examples

```
mod <- mrgsolve::house()
soloc(mod)
```

solversettings *Optional inputs for lsoda*

Description

These are settings for the differential equation solver (`lsoda`) that can be accessed via the R interface. The code listing below is taken directly from the `lsoda` source code.

Details

The following items can be set

- `hmax` (`HMAX` below); decrease `hmax` when you want to limit how big of a step the solver can take when integrating from one time to the next time. However be aware that smaller `hmax` will result in longer run times.
- `hmin` (`HMIN` below); don't fiddle with this unless you know what you're doing.
- `ixpr` (`IXPR` below)
- `maxsteps` (`MXSTEP` below); increase this number when the solver has a long interval between two integration times (e.g. when observation records are far apart).
- `mxhnil` (`MXHNIL` below); don't usually modify this one
- `atol` - the absolute solver tolerance; decrease this number (e.g. to 1E-10 or 1E-20 or 1E-50) when the value in a compartment can get extremely small; without this extra (lower) tolerance, the value can get so low that the number can randomly become negative. However be aware that more precision here will result in longer run times.
- `rtol` - the relative solver tolerances; decrease this number when you want a more precise solution. However be aware that more precision here will result in longer run times.

See Also

`aboutsolver`, `update`

summary.mrgmod *Print summary of a mrgmod object*

Description

Print summary of a mrgmod object

Usage

```
## S3 method for class 'mrgmod'
summary(object, ...)
```

Arguments

object	a mrgmod object
...	not used

---

tscale *Re-scale time in the simulated output*

Description

Re-scale time in the simulated output

Usage

```
tscale(x, value = 1, ...)
```

Arguments

x	model object.
value	value by which time will be scaled.
...	not used.

Details

There is also a `tscale` argument to `mrgsim()` that can be set to accomplish the same thing as a call to `tscale` in the pipeline.

Examples

```
# The model is in hours:
mod <- mrgsolve::house()

# The output is in days:
mod %>% tscale(1/24) %>% mrgsim()
```

update *Update the model object*

Description

After the model object is created, update various attributes.

Usage

```
## S4 method for signature 'mrgmod'
update(object, ..., merge = TRUE, open = FALSE, data = NULL, strict = TRUE)

## S4 method for signature 'omegalist'
update(object, y, ...)

## S4 method for signature 'sigmalist'
update(object, y, ...)

## S4 method for signature 'parameter_list'
update(object, .y, ...)
```

Arguments

object	a model object.
...	named items to update.
merge	logical indicating to merge (rather than replace) new and existing attributes.
open	logical; used only when merge is TRUE and parameter list or initial conditions list is being updated; if FALSE, no new items will be added; if TRUE, the parameter list may expand.
data	a list of items to update; this list is combined with any items passed in via ....
strict	if TRUE, a warning will be issued when there is an attempt to update a non-existent item.
y	another object involved in update
.y	data to update

Details

Slots that can be updated:

- verbose
- debug
- preclean
- mindt
- digits

- atol - absolute solver tolerance; see solversettings
- rtol - relative solver tolerance; see solversettings
- ss_rtol - relative tolerance when finding steady state
- ss_atol - absolute tolerance when finding steady state
- ixpr - see IXPR in solversettings
- mxhnil - see MXHNIL in solversettings
- hmin - see HMIN in solversettings
- hmax - see HMAX in solversettings
- maxsteps - see MXSTEP in solversettings
- start, end, delta, add
- tscale
- request
- param
- init
- omega
- sigma
- outvars

Value

The updated model object is returned.

See Also

update, mrgmod-class, within

Examples

```
## Not run:
 mod <- house()

 mod <- update(mod, end = 120, delta = 4, param = list(CL = 19.1))

## End(Not run)
```

use_custom_tol *Set up a model object to use either scalar or custom tolerances*

Description

Call `use_custom_tol()` to use custom relative and absolute tolerances in a model; call `use_scalar_tol()` to revert to the traditional configuration where a single `rtol` and `atol` are applied to all compartments.

Usage

```
use_custom_tol(x)

use_scalar_tol(x)
```

Arguments

`x`	a model object.

Details

If customized tolerances have not been initialized yet, they will be, assigning the current `rtol` or `atol` for every compartment. These default values can be updated using `custom_rtol()`, `custom_atol()`, or `custom_tol()`.

Value

An updated model object.

See Also

`custom_tol()`, `reset_tol()`, `get_tol()`

Examples

```
mod <- house()

mod <- use_custom_tol(mod)
mod

mod <- use_scalar_tol(mod)
mod
```

`valid_data_set` *Validate and prepare data sets for simulation*

Description

This function is called by `mrgsim()` and friends to check and prepare input data sets for simulation. Users may also call this function to pre-validate data when the same data set is used for repeated simulation.

Usage

```
valid_data_set(x, m = NULL, verbose = FALSE, quiet = FALSE)

valid_data_set.matrix(x, verbose = FALSE)
```

Arguments

`x`	data.frame or matrix.
`m`	a model object.
`verbose`	logical.
`quiet`	if `TRUE`, messages will be suppressed.

Details

An error will be issued when

- non-numeric data is found in columns sharing names with model parameters
- non-numeric data is found in reserved data items related to dosing (see `mrgsolve:::GLOBALS$CARRY_TRAN`)
- a column is found that is "internally classed", including columns that inherit from `integer64` (see `is.object()`)

Value

A matrix with non-numeric columns dropped; if x is a data.frame with character `cmt` column comprised of valid compartment names and `m` is a model object, the `cmt` column will be converted to the corresponding compartment number.

See Also

`valid_idata_set()`, `idata_set()`, `data_set()`

Examples

```
mod <- mrgsolve::house()

data(exTheoph)

d <- valid_data_set(exTheoph, mod)
```

`valid_idata_set` *Validate and prepare idata data sets for simulation*

Description

This function is called by `mrgsim()` and friends to check and prepare input data sets for simulation. Users may also call this function to pre-validate data when the same data set is used for repeated simulation.

Usage

```
valid_idata_set(x, m, verbose = FALSE, quiet = FALSE)
```

Arguments

`x`	data.frame or matrix.
`m`	a model object.
`verbose`	logical.
`quiet`	if `TRUE`, messages will be suppressed.

Details

An error will be issued when

- non-numeric data is found in columns sharing names with model parameters
- a column is found that is internally classed, including columns that inherit from `integer64` (see `is.object()`)

Value

A numeric matrix with class `valid_idata_set`.

See Also

`valid_data_set()`, `idata_set()`, `data_set()`

`within` *Update parameters, initials, and settings within a model object*

Description

The main use case for using within rather than update or param or init is when you want to update to a new value that is calculated from the existing value. See the example in details

Usage

```
## S3 method for class 'mrgmod'
within(data, expr, ...)
```

Arguments

`data`	an object with class mrgmod
`expr`	expressions evaluated in an environment containing various model object components, including parameters, initial conditions, and others (see details)
`...`	not used

Details

Other model object slots that can be updated: `start`, `end`, `delta`, `add`, `rtol`, `atol`, `hmax`, `maxsteps`. These are include for convenience, but we expect that most of the time these will get updated through the update method.

See Also

update

Examples

```
mod <- mrgsolve::house()

mod2 <- within(mod, {CL <- CL * 1.5})

mod$CL
mod2$CL
```

zero_re *Zero out random effects in a model object*

Description

Sets all elements of the OMEGA or SIGMA matrix to zero.

Usage

```
zero_re(.x, ...)

## S4 method for signature 'mrgmod'
zero_re(.x, ...)
```

Arguments

.x	a model object.
...	which matrix to zero out; pass omega to just zero out omega, sigma to just zero out sigma; passing nothing will zero out both.

Value

An updated object with elements of OMEGA and/or SIGMA set to zero.

Examples

```
mod <- house()
revar(mod)
mod <- zero_re(mod)
revar(mod)

## Not run:
mod <- modlib("popex", compile = FALSE)
mod <- zero_re(mod, omega)
revar(mod)

## End(Not run)
```

Index

∗ **datasets**
exdatasets, 45
∗ **param**
param, 88
*,tgrid,numeric-method *(*c,tgrid-method*)*, 20
*,tgrids,numeric-method *(*c,tgrid-method*)*, 20
+,tgrid,numeric-method *(*c,tgrid-method*)*, 20
+,tgrids,numeric-method *(*c,tgrid-method*)*, 20
[,mrgmod-method *(*$,mrgmod-method*)*, 8
[[,ev-method *(*$,ev-method*)*, 7
[[,mrgmod-method *(*$,mrgmod-method*)*, 8
$,ev-method, 7
$,mrgmod-method, 8

aboutsolver, *4*, 8, *107*
allparam *(*param*)*, 88
as.data.frame(), *74*
as.ev, 9
as.ev(), *36*, *40*
as.ev,data.frame-method *(*as.ev*)*, 9
as.ev,ev-method *(*as.ev*)*, 9
as.evd *(*evd*)*, 44
as.evd(), *36*
as.integer(), *85*
as.list,mrgmod-method, 10
as.list,mrgsims-method, 12
as.tbl.mrgsims *(*mrgsims_dplyr*)*, 76
as_bmat, 13
as_bmat(), *57*
as_bmat,ANY-method *(*as_bmat*)*, 13
as_bmat,data.frame-method *(*as_bmat*)*, 13
as_bmat,list-method *(*as_bmat*)*, 13
as_bmat,numeric-method *(*as_bmat*)*, 13
as_cmat *(*as_bmat*)*, 13
as_data_frame.mrgsims *(*mrgsims_dplyr*)*, 76
as_data_set, 14
as_data_set(), *74*
as_data_set,data.frame-method *(*as_data_set*)*, 14
as_data_set,ev-method *(*as_data_set*)*, 14
as_deslist, 16
as_dmat *(*as_bmat*)*, 13
as_dmat(), *57*
as_dmat,ANY-method *(*as_bmat*)*, 13
as_dmat,data.frame-method *(*as_bmat*)*, 13
as_dmat,list-method *(*as_bmat*)*, 13
as_dmat,numeric-method *(*as_bmat*)*, 13
as_tibble.mrgsims *(*mrgsims_dplyr*)*, 76
assign_ev *(*ev_assign*)*, 37

base::get(), *34*
BLOCK_PARSE, 17, *93*
blocks, 19
blocks,character-method *(*blocks*)*, 19
blocks,mrgmod-method *(*blocks*)*, 19
bmat *(*matrix_helpers*)*, 56
bmat(), *14*, *87*, *105*

c,matlist-method, 20
c,tgrid-method, 20
c,tgrids-method *(*c,tgrid-method*)*, 20
CAPTURE, *100*
CAPTURE *(*BLOCK_PARSE*)*, 17
carry.out *(*carry_out*)*, 21
carry_out, 21
check_data_names, 22
check_data_names(), *51*, *52*, *90*, *91*
cmat *(*matrix_helpers*)*, 56
cmat(), *13*, *14*, *87*, *105*
CMT *(*BLOCK_PARSE*)*, 17
cmtn, 23
cmtn,mrgmod-method *(*cmtn*)*, 23
code, 24
collapse_matrix, 24
collapse_matrix(), *26*

collapse_omega, 25
collapse_omega(), *24, 25*
collapse_sigma *(*collapse_omega*)*, 25
collapse_sigma(), *24, 25*
convert_fort_if *(*dsl_preprocess*)*, 31
convert_pow *(*dsl_preprocess*)*, 31
convert_semicolons *(*dsl_preprocess*)*, 31
custom_atol *(*custom_tol*)*, 26
custom_atol(), *111*
custom_rtol *(*custom_tol*)*, 26
custom_rtol(), *111*
custom_tol, 26
custom_tol(), *48*, *102*, *111*

data.table::fread(), *98*
data_set, 27, *35, 36*
data_set(), *14, 15*, *21*, *49*, *51*, *69*, *75*, *112, 113*
data_set,mrgmod,ANY-method *(*data_set*)*, 27
data_set,mrgmod,data.frame-method *(*data_set*)*, 27
data_set,mrgmod,ev-method *(*data_set*)*, 27
design, 29
details, 30
distinct.mrgsims *(*mrgsims_dplyr*)*, 76
dmat *(*matrix_helpers*)*, 56
dmat(), *13, 14*, *87*, *105*
do.mrgsims *(*mrgsims_dplyr*)*, 76
do_mrgsim *(*mrgsim*)*, 68
do_mrgsim(), *69*, *75*
dplyr::distinct(), *77*
dplyr::group_by(), *77*, *99*
dsl_preprocess, 31

env_eval, 33
env_get, 33
env_get(), *33*
env_get.mrgmod *(*env_get*)*, 33
env_get.mrgsims *(*env_get*)*, 33
env_get_env *(*env_get*)*, 33
env_get_env(), *33*
env_get_obj *(*env_get*)*, 33
env_ls, 34
env_ls(), *33*
env_update, 35
ev, 35
ev(), *15*, *29*, *41*, *44*, *49*
ev,ev-method *(*ev*)*, 35
ev,missing-method *(*ev*)*, 35
ev,mrgmod-method *(*ev*)*, 35
ev_assign, 37
ev_assign(), *36*
ev_days, 38
ev_days(), *36*
ev_expand *(*expand.idata*)*, 46
ev_methods, *36*
ev_rep, 39
ev_rep(), *36*
ev_repeat, 40
ev_repeat(), *36*, *39, 40*
ev_rx, 41
ev_rx,character,missing-method *(*ev_rx*)*, 41
ev_rx,mrgmod,character-method *(*ev_rx*)*, 41
ev_seq, 42
ev_seq(), *36*, *43*
evd, 44
evd(), *15*, *36*, *44*
evd,ev-method *(*evd*)*, 44
evd,missing-method *(*evd*)*, 44
evd,mrgmod-method *(*evd*)*, 44
evd_expand *(*expand.idata*)*, 46
exBoot *(*exdatasets*)*, 45
exdatasets, *29*, 45
exidata *(*exdatasets*)*, 45
expand.ev *(*expand.idata*)*, 46
expand.ev(), *15*
expand.evd *(*expand.idata*)*, 46
expand.evd(), *15*
expand.grid(), *46*
expand.idata, 46
expand_observations, 47
exTheoph *(*exdatasets*)*, 45
extran1 *(*exdatasets*)*, 45
extran2 *(*exdatasets*)*, 45
extran3 *(*exdatasets*)*, 45

filter.ev *(*mutate.ev*)*, 78
filter.mrgsims *(*mrgsims_dplyr*)*, 76
filter_sims *(*mrgsims_modify*)*, 77
FIXED *(*BLOCK_PARSE*)*, 17

get_tol, 48
get_tol(), *27*, *102*, *111*
get_tol_list *(*get_tol*)*, 48
group_by.mrgsims *(*mrgsims_dplyr*)*, 76

HANDLEMATRIX *(BLOCK_PARSE)*, 17

idata_set, 48
idata_set(), *21*, *29*, *51*, *69*, *75*, *96*, *112, 113*
idata_set,mrgmod,ANY-method *(idata_set)*, 48
idata_set,mrgmod,data.frame-method *(idata_set)*, 48
INIT *(BLOCK_PARSE)*, 17
init, 50, *114*
init(), *28*
init,ANY-method *(init)*, 50
init,list-method *(init)*, 50
init,missing-method *(init)*, 50
init,mrgmod-method *(init)*, 50
init,mrgsims-method *(init)*, 50
inventory, 51
inventory(), *89, 90*
is.mrgmod, 52
is.mrgsims, 53
is.object(), *112, 113*

knobs, 53

lattice::xyplot(), *94*
lctran, 54
lctran(), *15*, *28, 29*, *44*
loadso, 55
ls(), *34*

matrix_helpers, 56
mcode, 57
mcode(), *66*
mcode_cache *(mcode)*, 57
mcode_cache(), *57*, *66*
mcRNG, 58
merge.list(), *87*, *105*
modlib, 58
modlib(), *65, 66*
modlib_details, 59, *59*, *61, 62*, *66*
modlib_pk, *59*, 61, *66*
modlib_pkpd, *59*, 61, *66*
modlib_tmdd, *59*, 62, *66*
modlib_viral, *59*, 63, *66*
modMATRIX(), *87*, *105*
mread, 64
mread(), *5*, *32*, *57*, *67*, *79, 80*
mread_cache *(mread)*, 64
mread_cache(), *57, 58*
mread_file *(mread)*, 64
mread_yaml, 67
mread_yaml(), *80*
mrgsim, 68, *85*
mrgsim(), *21*, *73–75*, *96, 97*, *101*, *105*, *108*, *112, 113*
mrgsim_0 *(mrgsim_variants)*, 74
mrgsim_d *(mrgsim_variants)*, 74
mrgsim_d(), *73*
mrgsim_df *(mrgsim)*, 68
mrgsim_df(), *71*
mrgsim_di *(mrgsim_variants)*, 74
mrgsim_e *(mrgsim_variants)*, 74
mrgsim_ei *(mrgsim_variants)*, 74
mrgsim_ei(), *74*
mrgsim_i *(mrgsim_variants)*, 74
mrgsim_i(), *74*
mrgsim_q, 73
mrgsim_q(), *68*, *72*, *74, 75*, *97*
mrgsim_variants, *68*, *72*, 74, *74*, *97*
mrgsims, *72*
mrgsims_dplyr, 76, *77, 78*
mrgsims_modify, *76*, 77, *77*
mrgsolve *(mrgsolve-package)*, 4
mrgsolve-package, 4
mutate.ev, 78
mutate.ev(), *36*
mutate.mrgsims *(mrgsims_dplyr)*, 76
mutate_sims *(mrgsims_modify)*, 77
mwrite_cpp, 79
mwrite_yaml, 80
mwrite_yaml(), *67, 68*, *79*

names,mrgmod-method, 81
nmext, 81
nmext(), *98*
NMXML *(nmxml)*, 83
nmxml, 83
nmxml(), *83*
numericlist, *50*, *88, 89*
numerics_only, 85
numerics_only(), *29*

obsaug, 85
obsonly, 86
omat *(omega)*, 86
omat(), *25*
omat,list-method *(omega)*, 86
omat,matrix-method *(omega)*, 86

omat,missing-method (omega), 86
omat,mrgmod-method (omega), 86
omat,mrgsims-method (omega), 86
omat,NULL-method (omega), 86
omat,omegalist-method (omega), 86
OMEGA (omega), 86
omega, 86
options(), *65*
outvars, 88

PARAM (BLOCK_PARSE), 17
param, 88, *114*
param(), *49*
param,ANY-method (param), 88
param,list-method (param), 88
param,missing-method (param), 88
param,mrgmod-method (param), 88
param,mrgsims-method (param), 88
param_tags, 90
param_tags(), *22, 23*
parse_rx (ev_rx), 41
parse_rx(), *41*
PKMODEL, 91
PKMODEL(), *17*, *19*
plot (plot_mrgsims), 93
plot,mrgsims,character-method (plot_mrgsims), 93
plot,mrgsims,formula-method (plot_mrgsims), 93
plot,mrgsims,missing-method (plot_mrgsims), 93
plot_mrgsims, 93
plot_sims, 95
pull.mrgsims (mrgsims_dplyr), 76

qsim, 96
qsim(), *74, 75*

read_nmext, 98
read_nmext(), *83*
realize_addl, 99
realize_addl(), *36*
Req, 100
req (Req), 100
req.mrgmod (Req), 100
reserved, 101
reset_atol (reset_tol), 102
reset_rtol (reset_tol), 102
reset_tol, 102
reset_tol(), *27*, *48*, *111*
revar, 103
revar,mrgmod-method (revar), 103

see, 103
see(), *62*
see,mrgmod-method (see), 103
select.ev (mutate.ev), 78
select.mrgsims (mrgsims_dplyr), 76
select_sims (mrgsims_modify), 77
seq(), *43*
seq.ev (ev_seq), 42
set.seed(), *33*
SIGMA (sigma), 104
sigma, 104
signif(), *56*
simargs, 105
slice.mrgsims (mrgsims_dplyr), 76
smat (sigma), 104
smat(), *25*, *87*
smat,list-method (sigma), 104
smat,matrix-method (sigma), 104
smat,missing-method (sigma), 104
smat,mrgmod-method (sigma), 104
smat,mrgsims-method (sigma), 104
smat,NULL-method (sigma), 104
smat,sigmalist-method (sigma), 104
soloc, 106
solversettings, *11, 12*, 107, *110*
stime(), *70*
summarise.each (mrgsims_dplyr), 76
summarise.mrgsims (mrgsims_dplyr), 76
summary.mrgmod, 107

tempdir(), *57*, *106*
tgrid, *30*
tgrid_*_numeric (c,tgrid-method), 20
tgrid_+_numeric (c,tgrid-method), 20
tgrids_*_numeric (c,tgrid-method), 20
tgrids_+_numeric (c,tgrid-method), 20
THETA (BLOCK_PARSE), 17
tscale, 108

uctran (lctran), 54
uctran(), *15*, *28, 29*, *44*
update, *107*, 109, *110*, *114*
update(), *5*, *65*, *69*, *74, 75*, *97*
update,mrgmod-method (update), 109
update,omegalist-method (update), 109

update,parameter_list-method *(update)*, 109
update,sigmalist-method *(update)*, 109
use_custom_tol, 111
use_custom_tol(), *27*, *48*, *102*
use_scalar_tol *(use_custom_tol)*, 111
use_scalar_tol(), *27*, *48*, *102*
utils::read.table(), *98*

valid_data_set, 112
valid_data_set(), *29*, *113*
valid_idata_set, 113
valid_idata_set(), *29*, *112*

warn_int_div *(dsl_preprocess)*, 31
within, *110*, 114, *114*
within,mrgmod-method *(within)*, 114
within.mrgmod *(within)*, 114

yaml_to_cpp *(mread_yaml)*, 67
yaml_to_cpp(), *79*, *80*

zero_re, 115
zero_re,mrgmod-method *(zero_re)*, 115