Package: StressStrength (via r-universe)

July 19, 2024

Type Package

Title Computation and Estimation of Reliability of Stress-Strength Models

Version 1.0.2

Date 2016-04-29

Author Alessandro Barbiero <alessandro.barbiero@unimi.it>, Riccardo Inchingolo <dott.inchingolo_r@libero.it>

Maintainer Alessandro Barbiero <alessandro.barbiero@unimi.it>

Description Reliability of (normal) stress-strength models and for building two-sided or one-sided confidence intervals according to different approximate procedures.

License GPL

LazyLoad yes

Repository CRAN

Date/Publication 2016-05-01 00:44:38

NeedsCompilation no

Contents

StressStrength-package

Computation and Sample Estimation of Reliability of Stress-Strength Models

Description

Reliability of (normal) stress-strength models and for building two-side or one-side confidence intervals according to different approximate procedures.

Details

Package:	StressStrength
Type:	Package
Version:	1.0.2
Date:	2016-04-29
License:	GPL
LazyLoad:	yes

Author(s)

Alessandro Barbiero, Riccardo Inchingolo

Maintainer: Alessandro Barbiero <alessandro.barbiero@unimi.it>

References

Kotz S, Lumelskii Y, Pensky M (2003) The stress-strength model and its generalizations: theory and applications. World Scientific, Singapore

Guo H, Krishnamoorthy K (2004) New approximate inferential methods for the reliability parameter in a stress-strength model: The normal case. Commun Stat Theory Methods 33:1715-1731

estSSR

Sample estimation of reliability of stress-strength models

Description

The function provides sample estimates of reliability of stress-strength models, where stress and strength are modeled as independent r.v., whose distribution form is known except for the values of its parameters, assumed all unknown

Usage

```
estSSR(x, y, family="normal", twoside=TRUE, type="RG", alpha=0.05, B=2000)
```

Arguments

x	a random sample from r.v. X modeling strength
y	a random sample from r.v. Y modeling stress
family	the distribution of both X and Y
twoside	if TRUE, the function computes two-side confidence intervals; otherwise, one-side (a lower bound)
type	type of confidence interval (CI) to be built. For the normal family, "RG" stands for Reiser-Guttman, "AN" for large sample (asymptotically normal), "LOGIT" or "ARCSIN" for logit or arcsin variance stabilizing tranformations, "B" for percentile bootstrap, "GK" for Guo-Krishnamoorthy (one-sided only).
alpha	the complement to one of the nominal confidence level
B	number of bootstrap replicates (for type "B")

Details

For more details, please have a look at the references listed below

Value

A list comprising

ML_est	the sample value of the maximum likelihood estimator; for normal r.v. $\hat{R} = \Phi[(\bar{x} - \bar{y})/\sqrt{\hat{\sigma}_x^2 + \hat{\sigma}_y^2}]$, where $\bar{x}$ and $\bar{y}$ are the sample means, and $\hat{\sigma}_x^2$, $\hat{\sigma}_y^2$ the biased maximum likelihood variance estimators
Downton_est	(for normal r.v.) the sample value of one of the approximated UMVU estimators proposed by Downton $\hat{R}' = \Phi[(\bar{x} - \bar{y})/\sqrt{s_x^2 + s_y^2}]$
CI	the confidence interval
confidence_level	the nominal confidence level $1 - \alpha$

Author(s)

Alessandro Barbiero, Riccardo Inchingolo

References

Barbiero A (2011) Confidence Intervals for Reliability of Stress-Strength Models in the Normal Case, Comm Stat Sim Comp 40(6):907-925

Downton F. (1973) The Estimation of Pr (Y < X) in the Normal Case, Technometrics , 15(3):551-558

Kotz S, Lumelskii Y, Pensky M (2003) The stress-strength model and its generalizations: theory and applications. World Scientific, Singapore

Guo H, Krishnamoorthy K (2004) New approximate inferential methods for the reliability parameter in a stress-strength model: The normal case. Commun Stat Theory Methods 33:1715-1731

Mukherjee SP, Maiti SS (1998) Stress-strength reliability in the Weibull case. Frontiers In Reliability 4:231-248. WorldScientific, Singapore

Reiser BJ, Guttman I (1986) Statistical inference for P(Y<X): The normal case. Technometrics 28:253-257

See Also

SSR

Examples

```
# distributional parameters of X and Y
parx<-c(1, 1)
pary<-c(0, 2)
# sample sizes
n<-10
m<-20
# true value of R
SSR(parx,pary)
# draw independent random samples from X and Y
x<-rnorm(n, parx[1], parx[2])
y<-rnorm(m, pary[1], pary[2])
# build two-sided confidence intervals
estSSR(x, y, type="RG")
estSSR(x, y, type="AN")
estSSR(x, y, type="LOGIT")
estSSR(x, y, type="ARCSIN")
estSSR(x, y, type="B")
estSSR(x, y, type="B",B=1000) # change number of bootstrap replicates
# and one-sided
estSSR(x, y, type="RG", twoside=FALSE)
estSSR(x, y, type="AN", twoside=FALSE)
estSSR(x, y, type="LOGIT", twoside=FALSE)
estSSR(x, y, type="ARCSIN", twoside=FALSE)
estSSR(x, y, type="B", twoside=FALSE)
estSSR(x, y, type="GK", twoside=FALSE)
# changing sample sizes
n<-20
m<-30
x<-rnorm(n, parx[1], parx[2])
y<-rnorm(m, pary[1], pary[2])
# build tow-sided confidence intervals
estSSR(x, y, type="RG")
estSSR(x, y, type="AN")
estSSR(x, y, type="LOGIT")
estSSR(x, y, type="ARCSIN")
estSSR(x, y, type="B")
```

gkf *Numerical solution for an equation involving noncentral T cdf*

Description

It provides the solution of the equation $F_t(q; df, x) = p$, where F_t is the cdf (calculated in `q`) of a non-central Student r.v. with `df` degrees of freedom and unkwon noncentrality parameter x. In R code, gkf provides the solution of `pt(q,df,x)=p`.

Usage

```
gkf(p, q, df, eps = 1e-05)
```

Arguments

`p`	a probability
`q`	a real value
`df`	degrees of freedom of noncentral T
`eps`	tolerance

Details

This function is used for building Guo-Krishnamoorthy confidence intervals for R

Value

the noncentrality parameter x satisfying the equation $F_t(q; df, x) = p$

Author(s)

Alessandro Barbiero, Riccardo Inchingolo

References

Guo H, Krishnamoorthy K (2004) New approximate inferential methods for the reliability parameter in a stress-strength model: The normal case. Commun Stat Theory Methods 33:1715-1731

See Also

`estSSR`

Examples

```
p<-0.95
q<-5
df<-12
ncp<-gkf(p, q, df)
ncp
# check if the result is correct
pt(q, df, ncp)
# OK
# changing the tolerance
ncp<-gkf(p, q, df, eps=1e-10)
ncp
pt(q, df, ncp)
```

SSR *Computation of reliability of stress-strength models*

Description

For a stress-strength model, with independent r.v. X and Y representing the strength and the stress respectively, the function computes the reliability $R = P(X > Y)$

Usage

```
SSR(parx, pary, family = "normal")
```

Arguments

parx	parameters of X distribution (for the normal distribution, mean μ_x and standard deviation σ_x)
pary	parameters of Y distribution (for the normal distribution, mean μ_y and standard deviation σ_y)
family	family distribution for both X and Y (now, only "normal" available)

Details

The function computes $R = P(X > Y)$ where X and Y are independent r.v. following the family distribution with distributional parameters parx and pary.

Value

$R = P(X > Y)$. For normal distributions, $R = \Phi(d)$ with $d = (\mu_x - \mu_y)/\sqrt{\sigma_x^2 + \sigma_y^2}$.

Author(s)

Alessandro Barbiero, Riccardo Inchingolo

References

Kotz S, Lumelskii Y, Pensky M (2003) The stress-strength model and its generalizations: theory and applications. World Scientific, Singapore

See Also

estSSR

Examples

```
# let X be a normal r.v. with mean 1 and sd 1;
# and Y a normal r.v. with mean 0 and sd 2
# X and Y independent
parx<-c(1, 1)
pary<-c(0, 2)
# reliability of the stress-strength model (X=strength, Y=stress)
SSR(parx,pary)
# changing the parameters of Y
pary<-c(1.5, 2)
# reliability of the stress-strength model (X=strength, Y=stress)
SSR(parx,pary)
```

Index