

# Package: binsreg (via r-universe)

August 23, 2024

**Type** Package

**Title** Binscatter Estimation and Inference

**Date** 2024-07-23

**Version** 1.1

**Author** Matias D. Cattaneo, Richard K. Crump, Max H. Farrell, Yingjie Feng

**Maintainer** Yingjie Feng <fengyingjiepku@gmail.com>

**Description** Provides tools for statistical analysis using the binscatter methods developed by Cattaneo, Crump, Farrell and Feng (2024a) <[doi:10.48550/arXiv.1902.09608](https://doi.org/10.48550/arXiv.1902.09608)>, Cattaneo, Crump, Farrell and Feng (2024b) <[https://nppackages.github.io/references/Cattaneo-Crump-Farrell-Feng\\_2024\\_NonlinearBinscatter.pdf](https://nppackages.github.io/references/Cattaneo-Crump-Farrell-Feng_2024_NonlinearBinscatter.pdf)> and Cattaneo, Crump, Farrell and Feng (2024c) <[doi:10.48550/arXiv.1902.09615](https://doi.org/10.48550/arXiv.1902.09615)>. Binscatter provides a flexible way of describing the relationship between two variables based on partitioning/binning of the independent variable of interest. binsreg(), binsqreg() and binsglm() implement binscatter least squares regression, quantile regression and generalized linear regression respectively, with particular focus on constructing binned scatter plots. They also implement robust (pointwise and uniform) inference of regression functions and derivatives thereof. binstest() implements hypothesis testing procedures for parametric functional forms of and nonparametric shape restrictions on the regression function. binspwc() implements hypothesis testing procedures for pairwise group comparison of binscatter estimators. binsregselect() implements data-driven procedures for selecting the number of bins for binscatter estimation. All the commands allow for covariate adjustment, smoothness restrictions and clustering.

**Depends** R (>= 3.1)

**License** GPL-2

**Encoding** UTF-8

**Imports** ggplot2, sandwich, quantreg, splines, matrixStats

**RoxygenNote** 7.3.2

**NeedsCompilation** no

**Repository** CRAN

**Date/Publication** 2024-07-23 14:30:01 UTC

## Contents

binsreg-package . . . . .	2
binsglm . . . . .	3
binspwc . . . . .	9
binsqreg . . . . .	14
binsreg . . . . .	20
binsregselect . . . . .	26
binstest . . . . .	30
<b>Index</b>	<b>35</b>

---

binsreg-package      *Binsreg Package Document*

---

## Description

Binscatter provides a flexible, yet parsimonious way of visualizing and summarizing large data sets and has been a popular methodology in applied microeconomics and other social sciences. The binsreg package provides tools for statistical analysis using the binscatter methods developed in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). `binsreg` implements binscatter least squares regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. `binsqreg` implements binscatter quantile regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. `binsglm` implements binscatter generalized linear regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. `binstest` implements binscatter-based hypothesis testing procedures for parametric specifications of and shape restrictions on the unknown function of interest. `binspwc` implements hypothesis testing procedures for pairwise group comparison of binscatter estimators and plots confidence bands for the difference in binscatter parameters between each pair of groups. `binsregselect` implements data-driven number of bins selectors for binscatter implementation using either quantile-spaced or evenly-spaced binning/partitioning. All the commands allow for covariate adjustment, smoothness restrictions, and clustering, among other features.

The companion software article, [Cattaneo, Crump, Farrell and Feng \(2024c\)](#), provides further implementation details and empirical illustration. For related Stata, R and Python packages useful for nonparametric data analysis and statistical inference, visit <https://nppackages.github.io/>.

**Author(s)**

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepku@gmail.com>.

**References**

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

---

binsglm

*Data-Driven Binscatter Generalized Linear Regression with Robust Inference Procedures and Plots*

---

**Description**

binsglm implements binscatter generalized linear regression with robust inference procedures and plots, following the results in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). Binscatter provides a flexible way to describe the relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If the binning scheme is not set by the user, the companion function [binsregselect](#) is used to implement binscatter in a data-driven way. Hypothesis testing about the function of interest can be conducted via the companion function [binstest](#).

**Usage**

```
binsglm(y, x, w = NULL, data = NULL, at = NULL, family = gaussian(),
  deriv = 0, nolink = F, dots = NULL, dotsgrid = 0, dotsgridmean = T,
  line = NULL, linegrid = 20, ci = NULL, cigrid = 0, cigridmean = T,
  cb = NULL, cbgrid = 20, polyreg = NULL, polyreggrid = 20,
  polyregcigrid = 0, by = NULL, bycolors = NULL, bysymbols = NULL,
  bylpatterns = NULL, legendTitle = NULL, legendoff = F, nbins = NULL,
  binspos = "qs", binsmethod = "dpi", nbinsrot = NULL, pselect = NULL,
  sselect = NULL, samebinsby = F, randcut = NULL, nsims = 500,
  simsgrid = 20, simsseed = NULL, vce = "HC1", cluster = NULL,
  asyvar = F, level = 95, noplot = F, dfcheck = c(20, 30),
  masspoints = "on", weights = NULL, subset = NULL, plotxrange = NULL,
  plotyrange = NULL, ...)
```

**Arguments**

<code>y</code>	outcome variable. A vector.
<code>x</code>	independent variable of interest. A vector.
<code>w</code>	control variables. A matrix, a vector or a <a href="#">formula</a> .
<code>data</code>	an optional data frame containing variables in the model.
<code>at</code>	value of <code>w</code> at which the estimated function is evaluated. The default is <code>at="mean"</code> , which corresponds to the mean of <code>w</code> . Other options are: <code>at="median"</code> for the median of <code>w</code> , <code>at="zero"</code> for a vector of zeros. <code>at</code> can also be a vector of the same length as the number of columns of <code>w</code> (if <code>w</code> is a matrix) or a data frame containing the same variables as specified in <code>w</code> (when <code>data</code> is specified). Note that when <code>at="mean"</code> or <code>at="median"</code> , all factor variables (if specified) are excluded from the evaluation (set as zero).
<code>family</code>	a description of the error distribution and link function to be used in the generalized linear model. (See <a href="#">family</a> for details of family functions.)
<code>deriv</code>	derivative order of the regression function for estimation, testing and plotting. The default is <code>deriv=0</code> , which corresponds to the function itself. If <code>nolink=FALSE</code> , <code>deriv</code> cannot be greater than 1.
<code>nolink</code>	if true, the function within the inverse link function is reported instead of the conditional mean function for the outcome.
<code>dots</code>	a vector or a logical value. If <code>dots=c(p, s)</code> , a piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints is used for point estimation and plotting as "dots". The default is <code>dots=c(0, 0)</code> , which corresponds to piecewise constant (canonical <code>binscatter</code> ). If <code>dots=T</code> , the default <code>dots=c(0, 0)</code> is used unless the degree <code>p</code> or smoothness <code>s</code> selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>dots=F</code> is specified, the dots are not included in the plot.
<code>dotsgrid</code>	number of dots within each bin to be plotted. Given the choice, these dots are point estimates evaluated over an evenly-spaced grid within each bin. The default is <code>dotsgrid=0</code> , and only the point estimates at the mean of <code>x</code> within each bin are presented.
<code>dotsgridmean</code>	If true, the dots corresponding to the point estimates evaluated at the mean of <code>x</code> within each bin are presented. By default, they are presented, i.e., <code>dotsgridmean=T</code> .
<code>line</code>	a vector or a logical value. If <code>line=c(p, s)</code> , a piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints is used for plotting as a "line". If <code>line=T</code> is specified, <code>line=c(0, 0)</code> is used unless the degree <code>p</code> or smoothness <code>s</code> selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>line=F</code> or <code>line=NULL</code> is specified, the line is not included in the plot. The default is <code>line=NULL</code> .
<code>linegrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>line=c(p, s)</code> option. The default is <code>linegrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for fitting/plotting the line.
<code>ci</code>	a vector or a logical value. If <code>ci=c(p, s)</code> a piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints is used for constructing confidence intervals.

	If <code>ci=T</code> is specified, <code>ci=c(1,1)</code> is used unless the degree <code>p</code> or smoothness <code>s</code> selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>ci=F</code> or <code>ci=NULL</code> is specified, the confidence intervals are not included in the plot. The default is <code>ci=NULL</code> .
<code>cigrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>ci=c(p,s)</code> option. The default is <code>cigrid=1</code> , which corresponds to 1 evenly-spaced evaluation point within each bin for confidence interval construction.
<code>cigridmean</code>	If true, the confidence intervals corresponding to the point estimates evaluated at the mean of <code>x</code> within each bin are presented. The default is <code>cigridmean=T</code> .
<code>cb</code>	a vector or a logical value. If <code>cb=c(p,s)</code> , a the piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints is used for constructing the confidence band. If the option <code>cb=T</code> is specified, <code>cb=c(1,1)</code> is used unless the degree <code>p</code> or smoothness <code>s</code> selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>cb=F</code> or <code>cb=NULL</code> is specified, the confidence band is not included in the plot. The default is <code>cb=NULL</code> .
<code>cbgrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>cb=c(p,s)</code> option. The default is <code>cbgrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
<code>polyreg</code>	degree of a global polynomial regression model for plotting. By default, this fit is not included in the plot unless explicitly specified. Recommended specification is <code>polyreg=3</code> , which adds a cubic (global) polynomial fit of the regression function of interest to the binned scatter plot.
<code>polyreggrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>polyreg=p</code> option. The default is <code>polyreggrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
<code>polyregcigrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the <code>polyreg=p</code> option. The default is <code>polyregcigrid=0</code> , which corresponds to not plotting confidence intervals for the global polynomial regression approximation.
<code>by</code>	a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When <code>by</code> is specified, <code>binsreg</code> implements estimation and inference for each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option <code>samebinsby</code> below for imposing a common binning structure across subgroups.
<code>bycolors</code>	an ordered list of colors for plotting each subgroup series defined by the option <code>by</code> .
<code>bysymbols</code>	an ordered list of symbols for plotting each subgroup series defined by the option <code>by</code> .
<code>bylpatterns</code>	an ordered list of line patterns for plotting each subgroup series defined by the option <code>by</code> .

legendTitle	String, title of legend.
legendoff	If true, no legend is added.
nbins	number of bins for partitioning/binning of $x$ . If <code>nbins=T</code> or <code>nbins=NULL</code> (default) is specified, the number of bins is selected via the companion command <code>binsregselect</code> in a data-driven, optimal way whenever possible. If a vector with more than one number is specified, the number of bins is selected within this vector via the companion command <code>binsregselect</code> .
binspos	position of binning knots. The default is <code>binspos="qs"</code> , which corresponds to quantile-spaced binning (canonical <code>binscatter</code> ). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of inner knots (which must be within the range of $x$ ).
binsmethod	method for data-driven selection of the number of bins. The default is <code>binsmethod="dpi"</code> , which corresponds to the IMSE-optimal direct plug-in rule. The other option is: "rot" for rule of thumb implementation.
nbinsrot	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
pselect	vector of numbers within which the degree of polynomial $p$ for point estimation is selected. Piecewise polynomials of the selected optimal degree $p$ are used to construct dots or line if <code>dots=T</code> or <code>line=T</code> is specified, whereas piecewise polynomials of degree $p+1$ are used to construct confidence intervals or confidence band if <code>ci=T</code> or <code>cb=T</code> is specified. <i>Note:</i> To implement the degree or smoothness selection, in addition to <code>pselect</code> or <code>sselect</code> , <code>nbins=#</code> must be specified.
sselect	vector of numbers within which the number of smoothness constraints $s$ for point estimation is selected. Piecewise polynomials with the selected optimal $s$ smoothness constraints are used to construct dots or line if <code>dots=T</code> or <code>line=T</code> is specified, whereas piecewise polynomials with $s+1$ constraints are used to construct confidence intervals or confidence band if <code>ci=T</code> or <code>cb=T</code> is specified. If not specified, for each value $p$ supplied in the option <code>pselect</code> , only the piecewise polynomial with the maximum smoothness is considered, i.e., $s=p$ .
samebinsby	if true, a common partitioning/binning structure across all subgroups specified by the option <code>by</code> is forced. The knots positions are selected according to the option <code>binspos</code> and using the full sample. If <code>nbins</code> is not specified, then the number of bins is selected via the companion command <code>binsregselect</code> and using the full sample.
randcut	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which <code>runif()&lt;=#</code> are used. <code>#</code> must be between 0 and 1. By default, <code>max(5000, 0.01n)</code> observations are used if the samples size $n > 5000$ .
nsims	number of random draws for constructing confidence bands. The default is <code>nsims=500</code> , which corresponds to 500 draws from a standard Gaussian random vector of size $[(p+1)*J - (J-1)*s]$ . Setting at least <code>nsims=2000</code> is recommended to obtain the final results.
simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum operation needed to construct confidence bands. The default is <code>simsgrid=20</code> , which corresponds to 20 evenly-spaced evaluation

points within each bin for approximating the supremum operator. Setting at least `simsgrid=50` is recommended to obtain the final results.

<code>simsseed</code>	seed for simulation.
<code>vce</code>	Procedure to compute the variance-covariance matrix estimator. Options are <ul style="list-style-type: none"> <li>• "const" homoskedastic variance estimator.</li> <li>• "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.</li> <li>• "HC1" heteroskedasticity-robust plug-in residuals variance estimator with <code>hc1</code> weights. Default.</li> <li>• "HC2" heteroskedasticity-robust plug-in residuals variance estimator with <code>hc2</code> weights.</li> <li>• "HC3" heteroskedasticity-robust plug-in residuals variance estimator with <code>hc3</code> weights.</li> </ul>
<code>cluster</code>	cluster ID. Used for compute cluster-robust standard errors.
<code>asyvar</code>	if true, the standard error of the nonparametric component is computed and the uncertainty related to control variables is omitted. Default is <code>asyvar=FALSE</code> , that is, the uncertainty related to control variables is taken into account.
<code>level</code>	nominal confidence level for confidence interval and confidence band estimation. Default is <code>level=95</code> .
<code>noplot</code>	if true, no plot produced.
<code>dfcheck</code>	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is <code>dfcheck=c(20, 30)</code> . See <a href="#">Cattaneo, Crump, Farrell and Feng (2024c)</a> for more details.
<code>masspoints</code>	how mass points in $x$ are handled. Available options: <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
<code>weights</code>	an optional vector of weights to be used in the fitting process. Should be <code>NULL</code> or a numeric vector. For more details, see <a href="#">lm</a> .
<code>subset</code>	optional rule specifying a subset of observations to be used.
<code>plotxrange</code>	a vector. <code>plotxrange=c(min, max)</code> specifies a range of the x-axis for <code>binscatter</code> plot. Observations outside the range are dropped in the plot.
<code>plotyrange</code>	a vector. <code>plotyrange=c(min, max)</code> specifies a range of the y-axis for <code>binscatter</code> plot. Observations outside the range are dropped in the plot.
<code>...</code>	optional arguments used by <code>glm</code> .

**Value**

<code>bins_plot</code>	A ggplot object for binscatter plot.
<code>data.plot</code>	A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames: <ul style="list-style-type: none"> <li>• <code>data.dots</code> Data for dots. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.line</code> Data for line. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.ci</code> Data for CI. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>ci.l</code> and <code>ci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.cb</code> Data for CB. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>cb.l</code> and <code>cb.r</code>, left and right boundaries of the confidence band.</li> <li>• <code>data.poly</code> Data for polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.polyci</code> Data for confidence intervals based on polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>polyci.l</code> and <code>polyci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.bin</code> Data for the binning structure. It contains: <code>bin.id</code>, ID for each bin; <code>left.endpoint</code> and <code>right.endpoint</code>, left and right endpoints of each bin.</li> </ul>
<code>imse.var.rot</code>	Variance constant in IMSE, ROT selection.
<code>imse.bsq.rot</code>	Bias constant in IMSE, ROT selection.
<code>imse.var.dpi</code>	Variance constant in IMSE, DPI selection.
<code>imse.bsq.dpi</code>	Bias constant in IMSE, DPI selection.
<code>cval.by</code>	A vector of critical values for constructing confidence band for each group.
<code>opt</code>	A list containing options passed to the function, as well as <code>N.by</code> (total sample size for each group), <code>Ndist.by</code> (number of distinct values in <code>x</code> for each group), <code>Nclust.by</code> (number of clusters for each group), and <code>nbins.by</code> (number of bins for each group), and <code>byvals</code> (number of distinct values in <code>by</code> ). The degree and smoothness of polynomials for dots, line, confidence intervals and confidence band for each group are saved in <code>dots</code> , <code>line</code> , <code>ci</code> , and <code>cb</code> .

**Author(s)**

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepku@gmail.com>.



## References

- Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.
- Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.
- Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

## See Also

[binsregselect](#), [binstest](#).

## Examples

```
x <- runif(500); d <- 1*(runif(500)<=x)
## Binned scatterplot
binsglm(d, x, family=binomial())
```

---

binspwc

*Data-Driven Pairwise Group Comparison using Binscatter Methods*

---

## Description

binspwc implements hypothesis testing procedures for pairwise group comparison of binscatter estimators and plots confidence bands for the difference in binscatter parameters between each pair of groups, following the results in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). If the binning scheme is not set by the user, the companion function [binsregselect](#) is used to implement binscatter in a data-driven way. Binned scatter plots based on different methods can be constructed using the companion functions [binsreg](#), [binsqreg](#) or [binsglm](#). Hypothesis testing for parametric functional forms of and shape restrictions on the regression function of interest can be conducted via the companion function [binstest](#).

## Usage

```
binspwc(y, x, w = NULL, data = NULL, estmethod = "reg",
  family = gaussian(), quantile = NULL, deriv = 0, at = NULL,
  nolink = F, by = NULL, pwc = NULL, testtype = "two-sided",
  lp = Inf, bins = NULL, bynbins = NULL, binspos = "qs",
  pselect = NULL, sselect = NULL, binsmethod = "dpi", nbinsrot = NULL,
  samebinsby = FALSE, randcut = NULL, nsims = 500, simsgrid = 20,
  simsseed = NULL, vce = NULL, cluster = NULL, asyvar = F,
  dfcheck = c(20, 30), masspoints = "on", weights = NULL,
  subset = NULL, numdist = NULL, numclust = NULL, estmethodopt = NULL,
  plot = FALSE, dotsngrid = 0, plotxrange = NULL, plotyrange = NULL,
  colors = NULL, symbols = NULL, level = 95, ...)
```

**Arguments**

y	outcome variable. A vector.
x	independent variable of interest. A vector.
w	control variables. A matrix, a vector or a <a href="#">formula</a> .
data	an optional data frame containing variables used in the model.
estmethod	estimation method. The default is <code>estmethod="reg"</code> for tests based on <code>binscat</code> ter least squares regression. Other options are <code>"qreg"</code> for quantile regression and <code>"glm"</code> for generalized linear regression. If <code>estmethod="glm"</code> , the option family must be specified.
family	a description of the error distribution and link function to be used in the generalized linear model when <code>estmethod="glm"</code> . (See <a href="#">family</a> for details of family functions.)
quantile	the quantile to be estimated. A number strictly between 0 and 1.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is <code>deriv=0</code> , which corresponds to the function itself.
at	value of w at which the estimated function is evaluated. The default is <code>at="mean"</code> , which corresponds to the mean of w. Other options are: <code>at="median"</code> for the median of w, <code>at="zero"</code> for a vector of zeros. <code>at</code> can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when <code>at="mean"</code> or <code>at="median"</code> , all factor variables (if specified) are excluded from the evaluation (set as zero).
nolink	if true, the function within the inverse link function is reported instead of the conditional mean function for the outcome.
by	a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When <code>by</code> is specified, <code>binsreg</code> implements estimation and inference for each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option <code>samebinsby</code> below for imposing a common binning structure across subgroups.
pwc	a vector or a logical value. If <code>pwc=c(p,s)</code> , a piecewise polynomial of degree p with s smoothness constraints is used for testing the difference between groups. If <code>pwc=T</code> or <code>pwc=NULL</code> (default) is specified, <code>pwc=c(1,1)</code> is used unless the degree p or smoothness s selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ).
testtype	type of pairwise comparison test. The default is <code>testtype="two-sided"</code> , which corresponds to a two-sided test of the form $H_0: \mu_1(x) = \mu_2(x)$ . Other options are: <code>testtype="left"</code> for the one-sided test form $H_0: \mu_1(x) \leq \mu_2(x)$ and <code>testtype="right"</code> for the one-sided test of the form $H_0: \mu_1(x) \geq \mu_2(x)$ .
lp	an Lp metric used for pairwise comparison tests. The default is <code>lp=Inf</code> , which corresponds to the sup-norm of the t-statistic. Other options are <code>lp=q</code> for a positive number $q \geq 1$ . Note that <code>lp=Inf</code> ("sup-norm") has to be used for one-sided tests ( <code>testtype="left"</code> or <code>testtype="right"</code> ).

bins	A vector. If bins=c(p, s), it sets the piecewise polynomial of degree p with s smoothness constraints for data-driven (IMSE-optimal) selection of the partitioning/binning scheme. The default is bins=c(0, 0), which corresponds to the piecewise constant.
bynbins	a vector of the number of bins for partitioning/binning of x, which is applied to the binscatter estimation for each group. If a single number is specified, it is applied to the estimation for all groups. If bynbins=T or bynbins=NULL (default), the number of bins is selected via the companion function <a href="#">binsregselect</a> in a data-driven way whenever possible. <i>Note:</i> If a vector with more than one number is supplied, it is understood as the number of bins applied to binscatter estimation for each subgroup rather than the range for selecting the number of bins.
binspos	position of binning knots. The default is binspos="qs", which corresponds to quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of inner knots (which must be within the range of x).
pselect	vector of numbers within which the degree of polynomial p for point estimation is selected. If the selected optimal degree is p, then piecewise polynomials of degree p+1 are used to conduct pairwise group comparison. <i>Note:</i> To implement the degree or smoothness selection, in addition to pselect or sselect, bynbins=# must be specified.
sselect	vector of numbers within which the number of smoothness constraints s for point estimation is selected. If the selected optimal smoothness is s, then piecewise polynomials with s+1 smoothness constraints are used to conduct pairwise group comparison. If not specified, for each value p supplied in the option pselect, only the piecewise polynomial with the maximum smoothness is considered, i.e., s=p.
binsmethod	method for data-driven selection of the number of bins. The default is binsmethod="dpi", which corresponds to the IMSE-optimal direct plug-in rule. The other option is: "rot" for rule of thumb implementation.
nbinsrot	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
samebinsby	if true, a common partitioning/binning structure across all subgroups specified by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command <a href="#">binsregselect</a> and using the full sample.
randcut	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which <code>runif()&lt;=#</code> are used. # must be between 0 and 1. By default, <code>max(5000, 0.01n)</code> observations are used if the samples size <code>n&gt;5000</code> .
nsims	number of random draws for hypothesis testing. The default is nsims=500, which corresponds to 500 draws from a standard Gaussian random vector of size $[(p+1)*J - (J-1)*s]$ . Setting at least nsims=2000 is recommended to obtain the final results.

simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum (infimum or Lp metric) operation needed to construct hypothesis testing procedures. The default is <code>simsgrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for approximating the supremum (infimum or Lp metric) operator. Setting at least <code>simsgrid=50</code> is recommended to obtain the final results.
simsseed	seed for simulation.
vce	procedure to compute the variance-covariance matrix estimator. For least squares regression and generalized linear regression, the allowed options are the same as that for <code>binsreg</code> or <code>binsqreg</code> . For quantile regression, the allowed options are the same as that for <code>binsqreg</code> .
cluster	cluster ID. Used for compute cluster-robust standard errors.
asyvar	if true, the standard error of the nonparametric component is computed and the uncertainty related to control variables is omitted. Default is <code>asyvar=FALSE</code> , that is, the uncertainty related to control variables is taken into account.
dfcheck	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is <code>dfcheck=c(20, 30)</code> . See <a href="#">Cattaneo, Crump, Farrell and Feng (2024c)</a> for more details.
masspoints	how mass points in $x$ are handled. Available options: <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
weights	an optional vector of weights to be used in the fitting process. Should be <code>NULL</code> or a numeric vector. For more details, see <a href="#">lm</a> .
subset	optional rule specifying a subset of observations to be used.
numdist	number of distinct values for selection. Used to speed up computation.
numclust	number of clusters for selection. Used to speed up computation.
estmethodopt	a list of optional arguments used by <code>rq</code> (for quantile regression) or <code>glm</code> (for fitting generalized linear models).
plot	if true, the confidence bands for all pairwise group comparisons (the difference between each pair of groups) are plotted. The degree and smoothness of polynomials used to construct the bands are the same as those specified for testing. The default is <code>plot=F</code> , i.e., no plot is generated.

dotsngrid	number of dots to be added to the plot for confidence bands. Given the choice, these dots are point estimates of the difference between groups evaluated over an evenly-spaced grid within the common support of all groups. The default is <code>dotsngrid=0</code> , i.e., no point estimates are added. Whenever possible, the degree and smoothness of the polynomial for these point estimates are the same as those for selecting the number of bins; otherwise, the degree and smoothness specified for testing are used.
plotxrange	a vector. <code>plotxrange=c(min, max)</code> specifies a range of the x-axis for plotting. Observations outside the range are dropped in the plot.
plotyrange	a vector. <code>plotyrange=c(min, max)</code> specifies a range of the y-axis for plotting. Observations outside the range are dropped in the plot.
colors	an ordered list of colors for plotting the difference between each pair of groups.
symbols	an ordered list of symbols for plotting the difference between each pair of groups.
level	nominal confidence level for confidence band estimation. Default is <code>level=95</code> .
...	optional arguments to control bootstrapping if <code>estmethod="qreg"</code> and <code>vce="boot"</code> . See <a href="#">boot.rq</a> .

**Value**

stat	A matrix. Each row corresponds to the comparison between two groups. The first column is the test statistic. The second and third columns give the corresponding group numbers. The null hypothesis is $\mu_i(x) \leq \mu_j(x)$ , $\mu_i(x) = \mu_j(x)$ , or $\mu_i(x) \geq \mu_j(x)$ for group <i>i</i> (given in the second column) and group <i>j</i> (given in the third column). The group number corresponds to the list of group names given by <code>opt\$byvals</code> .
pval	A vector of p-values for all pairwise group comparisons.
bins_plot	A <code>ggplot</code> object for confidence bands plot.
data.plot	A list containing data for plotting. Each item is a sublist of data frames for comparison between each pair of groups. Each sublist may contain the following data frames: <ul style="list-style-type: none"> <li>• <code>data.dots</code> Data for dots. It contains: <code>pair</code>, the name for the pair of groups; <code>x</code>, evaluation points; <code>diff.fit</code>, point estimates of the group difference;</li> <li>• <code>data.cb</code> Data for confidence bands. It contains: <code>pair</code>, the name for the pair of groups; <code>x</code>, evaluation points; <code>cb.fit</code>, point estimates of the group difference; <code>cb.se</code>, standard errors; <code>cb.l</code> and <code>cb.r</code>, left and right boundaries of the confidence band.</li> </ul>
cval.cb	A vector of critical values for all pairwise group comparisons.
imse.var.rot	Variance constant in IMSE expansion, ROT selection.
imse.bsq.rot	Bias constant in IMSE expansion, ROT selection.
imse.var.dpi	Variance constant in IMSE expansion, DPI selection.
imse.bsq.dpi	Bias constant in IMSE expansion, DPI selection.
opt	A list containing options passed to the function, as well as <code>N.by</code> (total sample size for each group), <code>Ndist.by</code> (number of distinct values in <code>x</code> for each group), <code>Nclust.by</code> (number of clusters for each group), and <code>nbins.by</code> (number of bins for each group), and <code>byvals</code> (number of distinct values in <code>by</code> ).

**Author(s)**

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepku@gmail.com>.

**References**

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: **On Binscatter**. *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: **Nonlinear Binscatter Methods**. Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: **Binscatter Regressions**. Working Paper.

**See Also**

[binsreg](#), [binsqreg](#), [binsglm](#), [binsregselect](#), [binstest](#).

**Examples**

```
x <- runif(500); y <- sin(x)+rnorm(500); t <- 1*(runif(500)>0.5)
## Binned scatterplot
binspwc(y,x, by=t)
```

---

binsqreg

*Data-Driven Binscatter Quantile Regression with Robust Inference  
Procedures and Plots*

---

**Description**

binsqreg implements binscatter quantile regression with robust inference procedures and plots, following the results in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). Binscatter provides a flexible way to describe the quantile relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If the binning scheme is not set by the user, the companion function [binsregselect](#) is used to implement binscatter in a data-driven way. Hypothesis testing about the function of interest can be conducted via the companion function [binstest](#).

**Usage**

```
binsqreg(y, x, w = NULL, data = NULL, at = NULL, quantile = 0.5,
  deriv = 0, dots = NULL, dotsgrid = 0, dotsgridmean = T,
  line = NULL, linegrid = 20, ci = NULL, cigrid = 0, cigridmean = T,
  cb = NULL, cbgrid = 20, polyreg = NULL, polyreggrid = 20,
  polyregcigrid = 0, by = NULL, bycolors = NULL, bysymbols = NULL,
  bylpatterns = NULL, legendTitle = NULL, legendoff = F, nbins = NULL,
  binspos = "qs", binsmethod = "dpi", nbinsrot = NULL, pselect = NULL,
  sselect = NULL, samebinsby = F, randcut = NULL, nsims = 500,
  simsgrid = 20, simsseed = NULL, vce = "nid", cluster = NULL,
  asyvar = F, level = 95, noplot = F, dfcheck = c(20, 30),
  masspoints = "on", weights = NULL, subset = NULL, plotxrange = NULL,
  plotyrange = NULL, qregopt = NULL, ...)
```

**Arguments**

y	outcome variable. A vector.
x	independent variable of interest. A vector.
w	control variables. A matrix, a vector or a <a href="#">formula</a> .
data	an optional data frame containing variables in the model.
at	value of w at which the estimated function is evaluated. The default is at="mean", which corresponds to the mean of w. Other options are: at="median" for the median of w, at="zero" for a vector of zeros. at can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when at="mean" or at="median", all factor variables (if specified) are excluded from the evaluation (set as zero).
quantile	the quantile to be estimated. A number strictly between 0 and 1.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself.
dots	a vector or a logical value. If dots=c(p, s), a piecewise polynomial of degree p with s smoothness constraints is used for point estimation and plotting as "dots". The default is dots=c(0, 0), which corresponds to piecewise constant (canonical binscatter). If dots=T, the default dots=c(0, 0) is used unless the degree p or smoothness s selection is requested via the option pselect or sselect (see more details in the explanation of pselect and sselect). If dots=F is specified, the dots are not included in the plot.
dotsgrid	number of dots within each bin to be plotted. Given the choice, these dots are point estimates evaluated over an evenly-spaced grid within each bin. The default is dotsgrid=0, and only the point estimates at the mean of x within each bin are presented.
dotsgridmean	If true, the dots corresponding to the point estimates evaluated at the mean of x within each bin are presented. By default, they are presented, i.e., dotsgridmean=T.
line	a vector or a logical value. If line=c(p, s), a piecewise polynomial of degree p with s smoothness constraints is used for plotting as a "line". If line=T is

	specified, $\text{line}=\text{c}(0,0)$ is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>line=F</code> or <code>line=NULL</code> is specified, the line is not included in the plot. The default is <code>line=NULL</code> .
<code>linegrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>line=c(p,s)</code> option. The default is <code>linegrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for fitting/plotting the line.
<code>ci</code>	a vector or a logical value. If <code>ci=c(p,s)</code> a piecewise polynomial of degree $p$ with $s$ smoothness constraints is used for constructing confidence intervals. If <code>ci=T</code> is specified, <code>ci=c(1,1)</code> is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>ci=F</code> or <code>ci=NULL</code> is specified, the confidence intervals are not included in the plot. The default is <code>ci=NULL</code> .
<code>cigrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>ci=c(p,s)</code> option. The default is <code>cigrid=1</code> , which corresponds to 1 evenly-spaced evaluation point within each bin for confidence interval construction.
<code>cigridmean</code>	If true, the confidence intervals corresponding to the point estimates evaluated at the mean of $x$ within each bin are presented. The default is <code>cigridmean=T</code> .
<code>cb</code>	a vector or a logical value. If <code>cb=c(p,s)</code> , a the piecewise polynomial of degree $p$ with $s$ smoothness constraints is used for constructing the confidence band. If the option <code>cb=T</code> is specified, <code>cb=c(1,1)</code> is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>cb=F</code> or <code>cb=NULL</code> is specified, the confidence band is not included in the plot. The default is <code>cb=NULL</code> .
<code>cbgrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>cb=c(p,s)</code> option. The default is <code>cbgrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
<code>polyreg</code>	degree of a global polynomial regression model for plotting. By default, this fit is not included in the plot unless explicitly specified. Recommended specification is <code>polyreg=3</code> , which adds a cubic (global) polynomial fit of the regression function of interest to the binned scatter plot.
<code>polyreggrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the <code>polyreg=p</code> option. The default is <code>polyreggrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
<code>polyregcigrid</code>	number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the <code>polyreg=p</code> option. The default is <code>polyregcigrid=0</code> , which corresponds to not plotting confidence intervals for the global polynomial regression approximation.
<code>by</code>	a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When <code>by</code> is specified, <code>binsreg</code> implements estimation and inference for each subgroup separately, but produces a common



	binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option <code>samebinsby</code> below for imposing a common binning structure across subgroups.
<code>bycolors</code>	an ordered list of colors for plotting each subgroup series defined by the option <code>by</code> .
<code>bysymbols</code>	an ordered list of symbols for plotting each subgroup series defined by the option <code>by</code> .
<code>bylpatterns</code>	an ordered list of line patterns for plotting each subgroup series defined by the option <code>by</code> .
<code>legendTitle</code>	String, title of legend.
<code>legendoff</code>	If true, no legend is added.
<code>nbins</code>	number of bins for partitioning/binning of <code>x</code> . If <code>nbins=T</code> or <code>nbins=NULL</code> (default) is specified, the number of bins is selected via the companion command <code>binsregselect</code> in a data-driven, optimal way whenever possible. If a vector with more than one number is specified, the number of bins is selected within this vector via the companion command <code>binsregselect</code> .
<code>binspos</code>	position of binning knots. The default is <code>binspos="qs"</code> , which corresponds to quantile-spaced binning (canonical <code>binscatter</code> ). The other options are <code>"es"</code> for evenly-spaced binning, or a vector for manual specification of the positions of inner knots (which must be within the range of <code>x</code> ).
<code>binsmethod</code>	method for data-driven selection of the number of bins. The default is <code>binsmethod="dpi"</code> , which corresponds to the IMSE-optimal direct plug-in rule. The other option is: <code>"rot"</code> for rule of thumb implementation.
<code>nbinsrot</code>	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
<code>pselect</code>	vector of numbers within which the degree of polynomial <code>p</code> for point estimation is selected. Piecewise polynomials of the selected optimal degree <code>p</code> are used to construct dots or line if <code>dots=T</code> or <code>line=T</code> is specified, whereas piecewise polynomials of degree <code>p+1</code> are used to construct confidence intervals or confidence band if <code>ci=T</code> or <code>cb=T</code> is specified. <i>Note:</i> To implement the degree or smoothness selection, in addition to <code>pselect</code> or <code>sselect</code> , <code>nbins=#</code> must be specified.
<code>sselect</code>	vector of numbers within which the number of smoothness constraints <code>s</code> for point estimation is selected. Piecewise polynomials with the selected optimal <code>s</code> smoothness constraints are used to construct dots or line if <code>dots=T</code> or <code>line=T</code> is specified, whereas piecewise polynomials with <code>s+1</code> constraints are used to construct confidence intervals or confidence band if <code>ci=T</code> or <code>cb=T</code> is specified. If not specified, for each value <code>p</code> supplied in the option <code>pselect</code> , only the piecewise polynomial with the maximum smoothness is considered, i.e., <code>s=p</code> .
<code>samebinsby</code>	if true, a common partitioning/binning structure across all subgroups specified by the option <code>by</code> is forced. The knots positions are selected according to the option <code>binspos</code> and using the full sample. If <code>nbins</code> is not specified, then the number of bins is selected via the companion command <code>binsregselect</code> and using the full sample.
<code>randcut</code>	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which <code>runif()&lt;=#</code> are used.

	# must be between 0 and 1. By default, $\max(5000, 0.01n)$ observations are used if the samples size $n > 5000$ .
nsims	number of random draws for constructing confidence bands. The default is <code>nsims=500</code> , which corresponds to 500 draws from a standard Gaussian random vector of size $[(p+1)*J - (J-1)*s]$ . Setting at least <code>nsims=2000</code> is recommended to obtain the final results.
simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum operation needed to construct confidence bands. The default is <code>simsgrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for approximating the supremum operator. Setting at least <code>simsgrid=50</code> is recommended to obtain the final results.
simsseed	seed for simulation.
vce	Procedure to compute the variance-covariance matrix estimator (see <a href="#">summary.rq</a> for more details). Options are <ul style="list-style-type: none"> <li>• "iid" which presumes that the errors are iid and computes an estimate of the asymptotic covariance matrix as in KB(1978).</li> <li>• "nid" which presumes local (in quantile) linearity of the the conditional quantile functions and computes a Huber sandwich estimate using a local estimate of the sparsity.</li> <li>• "ker" which uses a kernel estimate of the sandwich as proposed by Powell (1991).</li> <li>• "boot" which implements one of several possible bootstrapping alternatives for estimating standard errors including a variate of the wild bootstrap for clustered response. See <a href="#">boot.rq</a> for further details.</li> </ul>
cluster	cluster ID. Used for compute cluster-robust standard errors.
asyvar	if true, the standard error of the nonparametric component is computed and the uncertainty related to control variables is omitted. Default is <code>asyvar=FALSE</code> , that is, the uncertainty related to control variables is taken into account.
level	nominal confidence level for confidence interval and confidence band estimation. Default is <code>level=95</code> .
noplot	if true, no plot produced.
dfcheck	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different statistical models considered. The default is <code>dfcheck=c(20, 30)</code> . See <a href="#">Cattaneo, Crump, Farrell and Feng (2024c)</a> for more details.
masspoints	how mass points in $x$ are handled. Available options: <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> </ul>

	<ul style="list-style-type: none"> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
weights	an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see <a href="#">lm</a> .
subset	optional rule specifying a subset of observations to be used.
plotxrange	a vector. <code>plotxrange=c(min, max)</code> specifies a range of the x-axis for plotting. Observations outside the range are dropped in the plot.
plotyrange	a vector. <code>plotyrange=c(min, max)</code> specifies a range of the y-axis for plotting. Observations outside the range are dropped in the plot.
qregopt	a list of optional arguments used by <a href="#">rq</a> .
...	optional arguments to control bootstrapping. See <a href="#">boot.rq</a> .

### Value

bins_plot	A ggplot object for binscatter plot.
data.plot	A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames: <ul style="list-style-type: none"> <li>• <code>data.dots</code> Data for dots. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.line</code> Data for line. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.ci</code> Data for CI. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>ci.l</code> and <code>ci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.cb</code> Data for CB. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>cb.l</code> and <code>cb.r</code>, left and right boundaries of the confidence band.</li> <li>• <code>data.poly</code> Data for polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.polyci</code> Data for confidence intervals based on polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>polyci.l</code> and <code>polyci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.bin</code> Data for the binning structure. It contains: <code>bin.id</code>, ID for each bin; <code>left.endpoint</code> and <code>right.endpoint</code>, left and right endpoints of each bin.</li> </ul>
<code>imse.var.rot</code>	Variance constant in IMSE, ROT selection.
<code>imse.bsq.rot</code>	Bias constant in IMSE, ROT selection.
<code>imse.var.dpi</code>	Variance constant in IMSE, DPI selection.
<code>imse.bsq.dpi</code>	Bias constant in IMSE, DPI selection.

`cval.by` A vector of critical values for constructing confidence band for each group.

`opt` A list containing options passed to the function, as well as `N.by` (total sample size for each group), `Ndist.by` (number of distinct values in `x` for each group), `Nclust.by` (number of clusters for each group), and `nbins.by` (number of bins for each group), and `byvals` (number of distinct values in `by`). The degree and smoothness of polynomials for `dots`, `line`, confidence intervals and confidence band for each group are saved in `dots`, `line`, `ci`, and `cb`.

### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepku@gmail.com>.

### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

### See Also

[binsregselect](#), [binstest](#).

### Examples

```
x <- runif(500); y <- sin(x)+rnorm(500)
## Binned scatterplot
binsreg(y,x)
```

---

binsreg

*Data-Driven Binscatter Least Squares Regression with Robust Inference Procedures and Plots*

---

### Description

`binsreg` implements binscatter least squares regression with robust inference procedures and plots, following the results in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). Binscatter provides a flexible way to describe the mean relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If

the binning scheme is not set by the user, the companion function `binsregselect` is used to implement `binscatter` in a data-driven (optimal) way. Hypothesis testing about the regression function can be conducted via the companion function `binstest`.

## Usage

```
binsreg(y, x, w = NULL, data = NULL, at = NULL, deriv = 0,
  dots = NULL, dotsgrid = 0, dotsgridmean = T, line = NULL,
  linegrid = 20, ci = NULL, cigrid = 0, cigridmean = T, cb = NULL,
  cbgrid = 20, polyreg = NULL, polyreggrid = 20, polyregcigrid = 0,
  by = NULL, bycolors = NULL, bysymbols = NULL, bylpatterns = NULL,
  legendTitle = NULL, legendoff = F, nbins = NULL, binspos = "qs",
  binsmethod = "dpi", nbinsrot = NULL, pselect = NULL, sselect = NULL,
  samebinsby = F, randcut = NULL, nsims = 500, simsgrid = 20,
  simsseed = NULL, vce = "HC1", cluster = NULL, asyvar = F,
  level = 95, noplot = F, dfcheck = c(20, 30), masspoints = "on",
  weights = NULL, subset = NULL, plotxrange = NULL, plotyrange = NULL)
```

## Arguments

<code>y</code>	outcome variable. A vector.
<code>x</code>	independent variable of interest. A vector.
<code>w</code>	control variables. A matrix, a vector or a <a href="#">formula</a> .
<code>data</code>	an optional data frame containing variables used in the model.
<code>at</code>	value of <code>w</code> at which the estimated function is evaluated. The default is <code>at="mean"</code> , which corresponds to the mean of <code>w</code> . Other options are: <code>at="median"</code> for the median of <code>w</code> , <code>at="zero"</code> for a vector of zeros. <code>at</code> can also be a vector of the same length as the number of columns of <code>w</code> (if <code>w</code> is a matrix) or a data frame containing the same variables as specified in <code>w</code> (when <code>data</code> is specified). Note that when <code>at="mean"</code> or <code>at="median"</code> , all factor variables (if specified) are excluded from the evaluation (set as zero).
<code>deriv</code>	derivative order of the regression function for estimation, testing and plotting. The default is <code>deriv=0</code> , which corresponds to the function itself.
<code>dots</code>	a vector or a logical value. If <code>dots=c(p, s)</code> , a piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints is used for point estimation and plotting as "dots". The default is <code>dots=c(0, 0)</code> , which corresponds to piecewise constant (canonical <code>binscatter</code> ). If <code>dots=T</code> , the default <code>dots=c(0, 0)</code> is used unless the degree <code>p</code> or smoothness <code>s</code> selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If <code>dots=F</code> is specified, the dots are not included in the plot.
<code>dotsgrid</code>	number of dots within each bin to be plotted. Given the choice, these dots are point estimates evaluated over an evenly-spaced grid within each bin. The default is <code>dotsgrid=0</code> , and only the point estimates at the mean of <code>x</code> within each bin are presented.
<code>dotsgridmean</code>	If true, the dots corresponding to the point estimates evaluated at the mean of <code>x</code> within each bin are presented. By default, they are presented, i.e., <code>dotsgridmean=T</code> .

line	a vector or a logical value. If $\text{line}=\text{c}(p, s)$ , a piecewise polynomial of degree $p$ with $s$ smoothness constraints is used for plotting as a "line". If $\text{line}=\text{T}$ is specified, $\text{line}=\text{c}(0, 0)$ is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If $\text{line}=\text{F}$ or $\text{line}=\text{NULL}$ is specified, the line is not included in the plot. The default is $\text{line}=\text{NULL}$ .
linegrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the $\text{line}=\text{c}(p, s)$ option. The default is $\text{linegrid}=20$ , which corresponds to 20 evenly-spaced evaluation points within each bin for fitting/plotting the line.
ci	a vector or a logical value. If $\text{ci}=\text{c}(p, s)$ a piecewise polynomial of degree $p$ with $s$ smoothness constraints is used for constructing confidence intervals. If $\text{ci}=\text{T}$ is specified, $\text{ci}=\text{c}(1, 1)$ is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If $\text{ci}=\text{F}$ or $\text{ci}=\text{NULL}$ is specified, the confidence intervals are not included in the plot. The default is $\text{ci}=\text{NULL}$ .
cigrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the $\text{ci}=\text{c}(p, s)$ option. The default is $\text{cigrid}=1$ , which corresponds to 1 evenly-spaced evaluation point within each bin for confidence interval construction.
cigridmean	If true, the confidence intervals corresponding to the point estimates evaluated at the mean of $x$ within each bin are presented. The default is $\text{cigridmean}=\text{T}$ .
cb	a vector or a logical value. If $\text{cb}=\text{c}(p, s)$ , a the piecewise polynomial of degree $p$ with $s$ smoothness constraints is used for constructing the confidence band. If the option $\text{cb}=\text{T}$ is specified, $\text{cb}=\text{c}(1, 1)$ is used unless the degree $p$ or smoothness $s$ selection is requested via the option <code>pselect</code> or <code>sselect</code> (see more details in the explanation of <code>pselect</code> and <code>sselect</code> ). If $\text{cb}=\text{F}$ or $\text{cb}=\text{NULL}$ is specified, the confidence band is not included in the plot. The default is $\text{cb}=\text{NULL}$ .
cbgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the $\text{cb}=\text{c}(p, s)$ option. The default is $\text{cbgrid}=20$ , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
polyreg	degree of a global polynomial regression model for plotting. By default, this fit is not included in the plot unless explicitly specified. Recommended specification is $\text{polyreg}=3$ , which adds a cubic (global) polynomial fit of the regression function of interest to the binned scatter plot.
polyreggrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the $\text{polyreg}=p$ option. The default is $\text{polyreggrid}=20$ , which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.
polyregcigrid	number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the $\text{polyreg}=p$ option. The default is $\text{polyregcigrid}=0$ , which corresponds to not plotting confidence intervals for the global polynomial regression approximation.

by	a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When by is specified, binsreg implements estimation and inference for each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option samebinsby below for imposing a common binning structure across subgroups.
bycolors	an ordered list of colors for plotting each subgroup series defined by the option by.
bysymbols	an ordered list of symbols for plotting each subgroup series defined by the option by.
bylpatterns	an ordered list of line patterns for plotting each subgroup series defined by the option by.
legendTitle	String, title of legend.
legendoff	If true, no legend is added.
nbins	number of bins for partitioning/binning of $x$ . If nbins=T or nbins=NULL (default) is specified, the number of bins is selected via the companion command <a href="#">binsregselect</a> in a data-driven, optimal way whenever possible. If a vector with more than one number is specified, the number of bins is selected within this vector via the companion command <a href="#">binsregselect</a> .
binspos	position of binning knots. The default is binspos="qs", which corresponds to quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of inner knots (which must be within the range of $x$ ).
binsmethod	method for data-driven selection of the number of bins. The default is binsmethod="dpi", which corresponds to the IMSE-optimal direct plug-in rule. The other option is: "rot" for rule of thumb implementation.
nbinsrot	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
pselect	vector of numbers within which the degree of polynomial $p$ for point estimation is selected. Piecewise polynomials of the selected optimal degree $p$ are used to construct dots or line if dots=T or line=T is specified, whereas piecewise polynomials of degree $p+1$ are used to construct confidence intervals or confidence band if ci=T or cb=T is specified. <i>Note:</i> To implement the degree or smoothness selection, in addition to pselect or sselect, nbins=# must be specified.
sselect	vector of numbers within which the number of smoothness constraints $s$ for point estimation is selected. Piecewise polynomials with the selected optimal $s$ smoothness constraints are used to construct dots or line if dots=T or line=T is specified, whereas piecewise polynomials with $s+1$ constraints are used to construct confidence intervals or confidence band if ci=T or cb=T is specified. If not specified, for each value $p$ supplied in the option pselect, only the piecewise polynomial with the maximum smoothness is considered, i.e., $s=p$ .
samebinsby	if true, a common partitioning/binning structure across all subgroups specified by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command <a href="#">binsregselect</a> and using the full sample.

randcut	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which $\text{runif}() \leq \#$ are used. $\#$ must be between 0 and 1. By default, $\max(5000, 0.01n)$ observations are used if the samples size $n > 5000$ .
nsims	number of random draws for constructing confidence bands. The default is $\text{nsims}=500$ , which corresponds to 500 draws from a standard Gaussian random vector of size $[(p+1)*J - (J-1)*s]$ . Setting at least $\text{nsims}=2000$ is recommended to obtain the final results.
simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum operation needed to construct confidence bands. The default is $\text{simsgrid}=20$ , which corresponds to 20 evenly-spaced evaluation points within each bin for approximating the supremum operator. Setting at least $\text{simsgrid}=50$ is recommended to obtain the final results.
simsseed	seed for simulation.
vce	Procedure to compute the variance-covariance matrix estimator. Options are <ul style="list-style-type: none"> <li>• "const" homoskedastic variance estimator.</li> <li>• "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.</li> <li>• "HC1" heteroskedasticity-robust plug-in residuals variance estimator with <math>\text{hc1}</math> weights. Default.</li> <li>• "HC2" heteroskedasticity-robust plug-in residuals variance estimator with <math>\text{hc2}</math> weights.</li> <li>• "HC3" heteroskedasticity-robust plug-in residuals variance estimator with <math>\text{hc3}</math> weights.</li> </ul>
cluster	cluster ID. Used for compute cluster-robust standard errors.
asyvar	If true, the standard error of the nonparametric component is computed and the uncertainty related to control variables is omitted. Default is $\text{asyvar}=\text{FALSE}$ , that is, the uncertainty related to control variables is taken into account.
level	nominal confidence level for confidence interval and confidence band estimation. Default is $\text{level}=95$ .
noplot	if true, no plot produced.
dfcheck	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different statistical models considered. The default is $\text{dfcheck}=\text{c}(20, 30)$ . See <a href="#">Cattaneo, Crump, Farrell and Feng (2024c)</a> for more details.
masspoints	how mass points in $x$ are handled. Available options: <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> </ul>



	<ul style="list-style-type: none"> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
weights	an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see <a href="#">lm</a> .
subset	Optional rule specifying a subset of observations to be used.
plotxrange	a vector. <code>plotxrange=c(min, max)</code> specifies a range of the x-axis for plotting. Observations outside the range are dropped in the plot.
plotyrange	a vector. <code>plotyrange=c(min, max)</code> specifies a range of the y-axis for plotting. Observations outside the range are dropped in the plot.

### Value

bins_plot	A ggplot object for binscatter plot.
data.plot	<p>A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames:</p> <ul style="list-style-type: none"> <li>• <code>data.dots</code> Data for dots. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.line</code> Data for line. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.ci</code> Data for CI. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>ci.l</code> and <code>ci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.cb</code> Data for CB. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>cb.l</code> and <code>cb.r</code>, left and right boundaries of the confidence band.</li> <li>• <code>data.poly</code> Data for polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; and <code>fit</code>, fitted values.</li> <li>• <code>data.polyci</code> Data for confidence intervals based on polynomial regression. It contains: <code>x</code>, evaluation points; <code>bin</code>, the indicator of bins; <code>isknot</code>, indicator of inner knots; <code>mid</code>, midpoint of each bin; <code>polyci.l</code> and <code>polyci.r</code>, left and right boundaries of each confidence intervals.</li> <li>• <code>data.bin</code> Data for the binning structure. It contains: <code>bin.id</code>, ID for each bin; <code>left.endpoint</code> and <code>right.endpoint</code>, left and right endpoints of each bin.</li> </ul>
imse.var.rot	Variance constant in IMSE, ROT selection.
imse.bsq.rot	Bias constant in IMSE, ROT selection.
imse.var.dpi	Variance constant in IMSE, DPI selection.
imse.bsq.dpi	Bias constant in IMSE, DPI selection.
cval.by	A vector of critical values for constructing confidence band for each group.

`opt` A list containing options passed to the function, as well as `N.by` (total sample size for each group), `Ndist.by` (number of distinct values in `x` for each group), `Nclust.by` (number of clusters for each group), and `nbins.by` (number of bins for each group), and `byvals` (number of distinct values in `by`). The degree and smoothness of polynomials for `dots`, `line`, confidence intervals and confidence band for each group are saved in `dots`, `line`, `ci`, and `cb`.

### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepku@gmail.com>.

### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

### See Also

[binsregselect](#), [binstest](#).

### Examples

```
x <- runif(500); y <- sin(x)+rnorm(500)
## Binned scatterplot
binsreg(y,x)
```

---

binsregselect	<i>Data-Driven IMSE-Optimal Partitioning/Binning Selection for Binscatter</i>
---------------	---

---

### Description

`binsregselect` implements data-driven procedures for selecting the number of bins for `binscatter` estimation. The selected number is optimal in minimizing integrated mean squared error (IMSE).

**Usage**

```
binsregselect(y, x, w = NULL, data = NULL, deriv = 0, bins = NULL,
  pselect = NULL, sselect = NULL, binspos = "qs", nbins = NULL,
  binsmethod = "dpi", nbinsrot = NULL, simsgrid = 20, savegrid = F,
  vce = "HC1", useeffn = NULL, randcut = NULL, cluster = NULL,
  dfcheck = c(20, 30), masspoints = "on", weights = NULL,
  subset = NULL, norotnorm = F, numdist = NULL, numclust = NULL)
```

**Arguments**

y	outcome variable. A vector.
x	independent variable of interest. A vector.
w	control variables. A matrix, a vector or a <a href="#">formula</a> .
data	an optional data frame containing variables used in the model.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is <code>deriv=0</code> , which corresponds to the function itself.
bins	a vector. <code>bins=c(p,s)</code> set a piecewise polynomial of degree <code>p</code> with <code>s</code> smoothness constraints for data-driven (IMSE-optimal) selection of the partitioning/binning scheme. By default, the function sets <code>bins=c(0,0)</code> , which corresponds to piecewise constant (canonical <code>binscatter</code> ).
pselect	vector of numbers within which the degree of polynomial <code>p</code> for point estimation is selected. <i>Note:</i> To implement the degree or smoothness selection, in addition to <code>pselect</code> or <code>sselect</code> , <code>nbins=#</code> must be specified.
sselect	vector of numbers within which the number of smoothness constraints <code>s</code> for point estimation is selected. If not specified, for each value <code>p</code> supplied in the option <code>pselect</code> , only the piecewise polynomial with the maximum smoothness is considered, i.e., <code>s=p</code> .
binspos	position of binning knots. The default is <code>binspos="qs"</code> , which corresponds to quantile-spaced binning (canonical <code>binscatter</code> ). The other option is <code>binspos="es"</code> for evenly-spaced binning.
nbins	number of bins for degree/smoothness selection. If <code>nbins=T</code> or <code>nbins=NULL</code> (default) is specified, the function selects the number of bins instead, given the specified degree and smoothness. If a vector with more than one number is specified, the command selects the number of bins within this vector.
binsmethod	method for data-driven selection of the number of bins. The default is <code>binsmethod="dpi"</code> , which corresponds to the IMSE-optimal direct plug-in rule. The other option is: <code>"rot"</code> for rule of thumb implementation.
nbinsrot	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum (infimum or $L_p$ metric) operation needed to construct confidence bands and hypothesis testing procedures. The default is <code>simsgrid=20</code> , which corresponds to 20 evenly-spaced evaluation points within each bin for approximating the supremum (infimum or $L_p$ metric) operator.

savegrid	if true, a data frame produced containing grid.
vce	<p>procedure to compute the variance-covariance matrix estimator. Options are</p> <ul style="list-style-type: none"> <li>• "const" homoskedastic variance estimator.</li> <li>• "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.</li> <li>• "HC1" heteroskedasticity-robust plug-in residuals variance estimator with hc1 weights. Default.</li> <li>• "HC2" heteroskedasticity-robust plug-in residuals variance estimator with hc2 weights.</li> <li>• "HC3" heteroskedasticity-robust plug-in residuals variance estimator with hc3 weights.</li> </ul>
useeffn	effective sample size to be used when computing the (IMSE-optimal) number of bins. This option is useful for extrapolating the optimal number of bins to larger (or smaller) datasets than the one used to compute it.
randcut	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which $\text{runif}() \leq \#$ are used. # must be between 0 and 1.
cluster	cluster ID. Used for compute cluster-robust standard errors.
dfcheck	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different statistical models considered. The default is <code>dfcheck=c(20, 30)</code> . See <a href="#">Cattaneo, Crump, Farrell and Feng (2024c)</a> for more details.
masspoints	<p>how mass points in <math>x</math> are handled. Available options:</p> <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
weights	an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see <a href="#">1m</a> .
subset	optional rule specifying a subset of observations to be used.
norotnorm	if true, a uniform density rather than normal density used for ROT selection.
numdist	number of distinct values for selection. Used to speed up computation.
numclust	number of clusters for selection. Used to speed up computation.

**Value**

<code>nbinsrot.poly</code>	ROT number of bins, unregularized.
<code>nbinsrot.regul</code>	ROT number of bins, regularized.
<code>nbinsrot.uknot</code>	ROT number of bins, unique knots.
<code>nbinsdpi</code>	DPI number of bins.
<code>nbinsdpi.uknot</code>	DPI number of bins, unique knots.
<code>prot.poly</code>	ROT degree of polynomials, unregularized.
<code>prot.regul</code>	ROT degree of polynomials, regularized.
<code>prot.uknot</code>	ROT degree of polynomials, unique knots.
<code>pdpi</code>	DPI degree of polynomials.
<code>pdpi.uknot</code>	DPI degree of polynomials, unique knots.
<code>srot.poly</code>	ROT number of smoothness constraints, unregularized.
<code>srot.regul</code>	ROT number of smoothness constraints, regularized.
<code>srot.uknot</code>	ROT number of smoothness constraints, unique knots.
<code>sdpi</code>	DPI number of smoothness constraints.
<code>sdpi.uknot</code>	DPI number of smoothness constraints, unique knots.
<code>imse.var.rot</code>	Variance constant in IMSE expansion, ROT selection.
<code>imse.bsq.rot</code>	Bias constant in IMSE expansion, ROT selection.
<code>imse.var.dpi</code>	Variance constant in IMSE expansion, DPI selection.
<code>imse.bsq.dpi</code>	Bias constant in IMSE expansion, DPI selection.
<code>int.result</code>	Intermediate results, including a matrix of degree and smoothness ( <code>deg_mat</code> ), the selected numbers of bins ( <code>vec.nbinsrot.poly</code> , <code>vec.nbinsrot.regul</code> , <code>vec.nbinsrot.uknot</code> , <code>vec.nbinsdpi</code> , <code>vec.nbinsdpi.uknot</code> ), and the bias and variance constants in IMSE ( <code>vec.imse.b.rot</code> , <code>vec.imse.v.rot</code> , <code>vec.imse.b.dpi</code> , <code>vec.imse.v.dpi</code> ) under each rule (ROT or DPI), corresponding to each pair of degree and smoothness (each row in <code>deg_mat</code> ).
<code>opt</code>	A list containing options passed to the function, as well as total sample size <code>n</code> , number of distinct values <code>Ndist</code> in <code>x</code> , and number of clusters <code>Nclust</code> .
<code>data.grid</code>	A data frame containing grid.

**Author(s)**

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepk@gmail.com>.

## References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

## See Also

[binsreg](#), [binstest](#).

## Examples

```
x <- runif(500); y <- sin(x)+rnorm(500)
est <- binsregselect(y,x)
summary(est)
```

---

binstest	<i>Data-Driven Nonparametric Shape Restriction and Parametric Model Specification Testing using Binscatter</i>
----------	--

---

## Description

`binstest` implements binscatter-based hypothesis testing procedures for parametric functional forms of and nonparametric shape restrictions on the regression function of interest, following the results in [Cattaneo, Crump, Farrell and Feng \(2024a\)](#) and [Cattaneo, Crump, Farrell and Feng \(2024b\)](#). If the binning scheme is not set by the user, the companion function [binsregselect](#) is used to implement binscatter in a data-driven way and inference procedures are based on robust bias correction. Binned scatter plots based on different methods can be constructed using the companion functions [binsreg](#), [binsqreg](#) or [binsglm](#).

## Usage

```
binstest(y, x, w = NULL, data = NULL, estmethod = "reg",
  family = gaussian(), quantile = NULL, deriv = 0, at = NULL,
  nolink = F, testmodel = NULL, testmodelparfit = NULL,
  testmodelpoly = NULL, testshape = NULL, testshapel = NULL,
  testshaper = NULL, testshape2 = NULL, lp = Inf, bins = NULL,
  nbins = NULL, pselect = NULL, sselect = NULL, binspos = "qs",
  binsmethod = "dpi", nbinsrot = NULL, randcut = NULL, nsims = 500,
  simsgrid = 20, simsseed = NULL, vce = NULL, cluster = NULL,
  asyvar = F, dfcheck = c(20, 30), masspoints = "on", weights = NULL,
  subset = NULL, numdist = NULL, numclust = NULL, estmethodopt = NULL,
  ...)
```

**Arguments**

y	outcome variable. A vector.
x	independent variable of interest. A vector.
w	control variables. A matrix, a vector or a <a href="#">formula</a> .
data	an optional data frame containing variables used in the model.
estmethod	estimation method. The default is estmethod="reg" for tests based on binscatter least squares regression. Other options are "qreg" for quantile regression and "glm" for generalized linear regression. If estmethod="glm", the option family must be specified.
family	a description of the error distribution and link function to be used in the generalized linear model when estmethod="glm". (See <a href="#">family</a> for details of family functions.)
quantile	the quantile to be estimated. A number strictly between 0 and 1.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself.
at	value of w at which the estimated function is evaluated. The default is at="mean", which corresponds to the mean of w. Other options are: at="median" for the median of w, at="zero" for a vector of zeros. at can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when at="mean" or at="median", all factor variables (if specified) are excluded from the evaluation (set as zero).
nolink	if true, the function within the inverse link function is reported instead of the conditional mean function for the outcome.
testmodel	a vector or a logical value. It sets the degree of polynomial and the number of smoothness constraints for parametric model specification testing. If testmodel=c(p,s) is specified, a piecewise polynomial of degree p with s smoothness constraints is used. If testmodel=T or testmodel=NULL (default) is specified, testmodel=c(1,1) is used unless the degree p or the smoothness s selection is requested via the option pselect or sselect (see more details in the explanation of pselect and sselect).
testmodelparfit	a data frame or matrix which contains the evaluation grid and fitted values of the model(s) to be tested against. The column contains a series of evaluation points at which the binscatter model and the parametric model of interest are compared with each other. Each parametric model is represented by other columns, which must contain the fitted values at the corresponding evaluation points.
testmodelpoly	degree of a global polynomial model to be tested against.
testshape	a vector or a logical value. It sets the degree of polynomial and the number of smoothness constraints for nonparametric shape restriction testing. If testshape=c(p,s) is specified, a piecewise polynomial of degree p with s smoothness constraints is used. If testshape=T or testshape=NULL (default) is specified, testshape=c(1,1) is used unless the degree p or smoothness s selection is requested via the option pselect or sselect (see more details in the explanation of pselect and sselect).

testshape1	a vector of null boundary values for hypothesis testing. Each number $a$ in the vector corresponds to one boundary of a one-sided hypothesis test to the left of the form $H_0: \sup_x \mu(x) \leq a$ .
testshaper	a vector of null boundary values for hypothesis testing. Each number $a$ in the vector corresponds to one boundary of a one-sided hypothesis test to the right of the form $H_0: \inf_x \mu(x) \geq a$ .
testshape2	a vector of null boundary values for hypothesis testing. Each number $a$ in the vector corresponds to one boundary of a two-sided hypothesis test of the form $H_0: \sup_x  \mu(x) - a  = 0$ .
lp	an $L_p$ metric used for parametric model specification testing and/or shape restriction testing. The default is $lp = \text{Inf}$ , which corresponds to the sup-norm of the t-statistic. Other options are $lp = q$ for a positive number $q \geq 1$ . Note that $lp = \text{Inf}$ ("sup-norm") has to be used for testing one-sided shape restrictions.
bins	a vector. If $\text{bins} = c(p, s)$ , it sets the piecewise polynomial of degree $p$ with $s$ smoothness constraints for data-driven (IMSE-optimal) selection of the partitioning/binning scheme. The default is $\text{bins} = c(0, 0)$ , which corresponds to the piecewise constant.
nbins	number of bins for partitioning/binning of $x$ . If $\text{nbins} = T$ or $\text{nbins} = \text{NULL}$ (default) is specified, the number of bins is selected via the companion command <a href="#">binsregselect</a> in a data-driven, optimal way whenever possible. If a vector with more than one number is specified, the number of bins is selected within this vector via the companion command <a href="#">binsregselect</a> .
pselect	vector of numbers within which the degree of polynomial $p$ for point estimation is selected. If the selected optimal degree is $p$ , then piecewise polynomials of degree $p+1$ are used to conduct testing for nonparametric shape restrictions or parametric model specifications. <i>Note:</i> To implement the degree or smoothness selection, in addition to <code>pselect</code> or <code>sselect</code> , <code>nbins=#</code> must be specified.
sselect	vector of numbers within which the number of smoothness constraints $s$ for point estimation is selected. If the selected optimal smoothness is $s$ , then piecewise polynomials of $s+1$ smoothness constraints are used to conduct testing for nonparametric shape restrictions or parametric model specifications. If not specified, for each value $p$ supplied in the option <code>pselect</code> , only the piecewise polynomial with the maximum smoothness is considered, i.e., $s=p$ .
binspos	position of binning knots. The default is <code>binspos="qs"</code> , which corresponds to quantile-spaced binning (canonical <code>binscatter</code> ). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of inner knots (which must be within the range of $x$ ).
binsmethod	method for data-driven selection of the number of bins. The default is <code>binsmethod="dpi"</code> , which corresponds to the IMSE-optimal direct plug-in rule. The other option is: "rot" for rule of thumb implementation.
nbinsrot	initial number of bins value used to construct the DPI number of bins selector. If not specified, the data-driven ROT selector is used instead.
randcut	upper bound on a uniformly distributed variable used to draw a subsample for bins/degree/smoothness selection. Observations for which <code>runif() &lt;=#</code> are used. <code>#</code> must be between 0 and 1. By default, <code>max(5000, 0.01n)</code> observations are used if the samples size $n > 5000$ .



nsims	number of random draws for hypothesis testing. The default is nsims=500, which corresponds to 500 draws from a standard Gaussian random vector of size $[(p+1)*J - (J-1)*s]$ . Setting at least nsims=2000 is recommended to obtain the final results.
simsgrid	number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum (infimum or $L_p$ metric) operation needed to construct hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for approximating the supremum (infimum or $L_p$ metric) operator. Setting at least simsgrid=50 is recommended to obtain the final results.
simsseed	seed for simulation.
vce	procedure to compute the variance-covariance matrix estimator. For least squares regression and generalized linear regression, the allowed options are the same as that for binsreg or binsqreg. For quantile regression, the allowed options are the same as that for binsqreg.
cluster	cluster ID. Used for compute cluster-robust standard errors.
asyvar	if true, the standard error of the nonparametric component is computed and the uncertainty related to control variables is omitted. Default is asyvar=FALSE, that is, the uncertainty related to control variables is taken into account.
dfcheck	adjustments for minimum effective sample size checks, which take into account number of unique values of $x$ (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20, 30). See Cattaneo, Crump, Farrell and Feng (2024c) for more details.
masspoints	how mass points in $x$ are handled. Available options: <ul style="list-style-type: none"> <li>• "on" all mass point and degrees of freedom checks are implemented. Default.</li> <li>• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.</li> <li>• "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.</li> <li>• "off" "noadjust" and "nolocalcheck" are set simultaneously.</li> <li>• "veryfew" forces the function to proceed as if <math>x</math> has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.</li> </ul>
weights	an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see <a href="#">lm</a> .
subset	optional rule specifying a subset of observations to be used.
numdist	number of distinct values for selection. Used to speed up computation.
numclust	number of clusters for selection. Used to speed up computation.
estmethodopt	a list of optional arguments used by <a href="#">rq</a> (for quantile regression) or <a href="#">glm</a> (for fitting generalized linear models).
...	optional arguments to control bootstrapping if estmethod="qreg" and vce="boot". See <a href="#">boot.rq</a> .

**Value**

testshapeL	Results for testshapeL, including: testvalL, null boundary values; stat.shapeL, test statistics; and pval.shapeL, p-value.
testshapeR	Results for testshaper, including: testvalR, null boundary values; stat.shapeR, test statistics; and pval.shapeR, p-value.
testshape2	Results for testshape2, including: testval2, null boundary values; stat.shape2, test statistics; and pval.shape2, p-value.
testpoly	Results for testmodelpoly, including: testpoly, the degree of global polynomial; stat.poly, test statistic; pval.poly, p-value.
testmodel	Results for testmodelparfit, including: stat.model, test statistics; pval.model, p-values.
imse.var.rot	Variance constant in IMSE, ROT selection.
imse.bsq.rot	Bias constant in IMSE, ROT selection.
imse.var.dpi	Variance constant in IMSE, DPI selection.
imse.bsq.dpi	Bias constant in IMSE, DPI selection.
opt	A list containing options passed to the function, as well as total sample size n, number of distinct values Ndist in x, number of clusters Nclust, and number of bins nbins.

**Author(s)**

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, UC Santa Barbara, Santa Barbara, CA. <mhfarrell@gmail.com>.

Yingjie Feng (maintainer), Tsinghua University, Beijing, China. <fengyingjiepk@gmail.com>.

**References**

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024a: [On Binscatter](#). *American Economic Review* 114(5): 1488-1514.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024b: [Nonlinear Binscatter Methods](#). Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2024c: [Binscatter Regressions](#). Working Paper.

**See Also**

[binsreg](#), [binsqreg](#), [binsglm](#), [binsregselect](#).

**Examples**

```
x <- runif(500); y <- sin(x)+rnorm(500)
est <- binstest(y,x, testmodelpoly=1)
summary(est)
```

# Index

`binsglm`, [2](#), [3](#), [9](#), [14](#), [30](#), [34](#)  
`binspwc`, [2](#), [9](#)  
`binsqreg`, [2](#), [9](#), [12](#), [14](#), [14](#), [30](#), [33](#), [34](#)  
`binsreg`, [2](#), [9](#), [12](#), [14](#), [20](#), [30](#), [33](#), [34](#)  
`binsreg-package`, [2](#)  
`binsregselect`, [2](#), [3](#), [6](#), [9](#), [11](#), [14](#), [17](#), [20](#), [21](#),  
[23](#), [26](#), [26](#), [30](#), [32](#), [34](#)  
`binstest`, [2](#), [3](#), [9](#), [14](#), [20](#), [21](#), [26](#), [30](#), [30](#)  
`boot.rq`, [13](#), [18](#), [19](#), [33](#)

`family`, [4](#), [10](#), [31](#)  
`formula`, [4](#), [10](#), [15](#), [21](#), [27](#), [31](#)

`glm`, [7](#), [12](#), [33](#)

`lm`, [7](#), [12](#), [19](#), [25](#), [28](#), [33](#)

`rq`, [12](#), [19](#), [33](#)

`summary.rq`, [18](#)